

Windows SETUP.INF Complete Reference

Complete Windows Installation Guide

About the Setup Program

The Windows Setup program is located on Disk #1 of the Microsoft Windows disk set. The installation process consists of two main stages:

- **Stage 1: MS-DOS Mode Setup**
 1. The program evaluates the computer system configuration
 2. Requests verification of the detected information
 3. Copies basic Windows files to the system's hard disk
- **Stage 2: Windows Mode Setup**
 1. Loads the Windows operating system
 2. Installs the remaining system files
 3. Guides through a series of choices for installing printer drivers and other applications

Running the Setup Program

For initial installation:

1. Insert Windows Disk #1 into the floppy drive
2. Switch to the appropriate drive letter (for example, A:)
3. At the command prompt, type: setup
4. Press the ENTER key
5. Follow the instructions on your screen
6. Use the F1 key for online help

For configuration changes:

1. Run Setup from Program Manager after Windows is installed
2. Use to change system configuration
3. Add or remove system files

Command Line Parameters

Parameter	Purpose
/i	Ignores automatic hardware detection. The user will have to check settings and possibly make corrections on the System Information screen during Setup.
/n	Sets up a shared copy of Windows from a network server.
/a	Begins Administrative Setup by expanding and copying all files from the Windows installation disks onto a network server, and also marking the files as read-only.
/b	Sets up Windows with monochrome display attributes.
/t	Searches the drive for incompatible software that should not run at the same time as Setup or Windows. (For maintenance only.)

/h:[filename]	Runs Batch Mode Setup to install Windows with little or no user interaction. The filename is the name of the system settings file that contains information about the user's configuration.
/o:[filename]	Specifies the SETUP.INF file, including the path if filename is not in the directory that contains the Windows Setup files.
/s:[filename]	Specifies the SETUP.INF file, including a path for the Windows installation disks.

Help Tip: To see a list of the switches available for Windows Setup, at the command prompt type `setup /?` and press ENTER.

Express Setup vs. Custom Setup

Express Setup:

1. Recommended for most standard installations
2. Requires providing information only about printers and port connections
3. Automatically detects the system hardware

Custom Setup:

1. Provides precise control over how Windows is set up
2. Requires verification of information detected about the hardware and software in your system
3. Allows selection of:
 - The directory where you want the Windows files installed
 - The computer system hardware, including the monitor, mouse, and keyboard
 - The preferred language
 - The network configuration, if any
 - The printers and printer ports for the computer system
 - The other applications you want to run with Windows
 - The specific Windows components you want to install

Custom Installation Strategies

For single system:

- Customize installation process: Choose Custom Setup at the first Setup prompt
- Customize after installation: Use Control Panel, Program Manager, and Windows Setup

For multiple systems:

- Network installation: Use `setup /a` to copy files to the network server, then use `setup /n` to install a shared copy of Windows on the workstations
- Automated installation: Create custom system settings files and use `setup /h`
- Hardware list customization: Edit device entries in SETUP.INF for hardware, and edit printer entries in CONTROL.INF
- Application customization: Install custom applications, customize Windows applications installation, install custom PIFs during installation

Critical Important Notes

- Do not use the MS-DOS copy command to copy the Windows files from the Setup disks
- These files are compressed and cannot be used unless you run the Setup program
- Setup renames the compressed files during installation
- Files on your system that end with an underscore (_) are compressed and have not been installed properly

Technical details

Introduction

SETUP.INF is the master configuration file that controls every aspect of Windows installation. This comprehensive reference documents all sections, keys, and installation processes based on the original Windows Resource Kit documentation.

Installation Process Overview

The Windows installation follows this precise sequence:

Phase 1: Initialization

1. Read [setup] section for help file location
2. Process [data] section for system requirements and defaults
3. Initialize disk definitions from [disks] and [oemdisks]
4. Load dialog text from [dialog] section

Phase 2: File Copying

1. Copy SETUP.EXE to WINDOWS and and SETUP.INF to SYSTEM directory
2. Copy system files from [windows.system] section
3. Copy core Windows files from [windows] section
4. Copy 386-specific files from [windows.system.386]
5. Install display drivers from [display] section
6. Install keyboard drivers from keyboard sections
7. Install mouse drivers from pointing device sections
8. Copy network components if selected
9. Install fonts based on display resolution

Phase 3: Configuration

1. Update INI files based on [ini.upd.patches] and [ini.upd.31]
2. Create Program Manager groups
3. Run post-installation programs from [run] section

Phase 4: Finalization

1. Process [blowaway] section to mark installation end
2. Clean up temporary files

General Installation Sections

[setup] Section

Defines the Setup help file location.

Format:

```
[setup]  
help=filename.hlp
```

Parameters:

Parameter	Value	Description
-----	-----	-----
help	setup.hlp	Specifies the help file for Setup program

Example:

```
[setup]  
help=setup.hlp
```

[run] Section

Specifies programs to execute after Setup completion.

Format:

```
[run]  
"program_name"
```

Parameters:

Parameter	Description
-----	-----
program_name	Executable to run after installation

Example:

```
[run]  
"control" ; Runs Control Panel after Setup
```

[dialog] Section

Contains all text strings displayed in Setup dialog boxes.

Complete Standard Entries:

```
[dialog]
caption = "Windows Setup"
exit = "Exit Windows Setup"
title = "Installing Windows 3.1"
options = "In addition to installing Windows 3.1, you can:"
printwait = "Please wait while Setup configures your printer(s)..."
copywait = "Welcome to Microsoft Windows 3.1 ! ..."
```

[winexec] Section

Provides core file information for Windows Mode Setup.

Complete Standard Entries:

```
[winexec]
execstd= "dosx.exe" ; MS-DOS Extender for standard mode
execcmd= "krnl286.exe lb /q:" ; Command and switches for kernel
exechemem= "xmsmmgr.exe" ; Extended memory manager for Setup
himemcmd= "" ; Switches for HIMEM.SYS
Krnl386= 2:krnl386.exe ; Kernel for 386 enhanced mode
Krnl286= 2:krnl286.exe ; Kernel for standard mode
dosx= 2:dosx.exe ; Disk location for DOSX.EXE file
```

[data] Section

Defines system requirements, defaults, and installation parameters.

Disk Space Requirements (in bytes):

```
[data]
netadmin= 16000000 ; 16.0 MB
netadminupd= 16000000 ; 16.0 MB
upd2x386full= 10500000,8000000 ; 10.5 MB, 8.0 MB
upd2x386net= 300000 ; 0.3 MB
upd3x386full= 5500000,5000000 ; 5.5 MB, 5.0 MB
upd3x386net= 300000 ; 0.3 MB
upd2x286full= 9000000,6500000 ; 9.0 MB, 6.5 MB
upd2x286net= 300000 ; 0.3 MB
upd3x286full= 5500000,5000000 ; 5.5 MB, 5.0 MB
upd3x286net= 300000 ; 0.3 MB
new386full= 10500000,8000000 ; 10.5 MB, 8.0 MB
new286full= 9000000,6500000 ; 9.0 MB, 6.5 MB
new386net= 300000,300000 ; 0.3 MB, 0.3 MB
new286net= 300000,300000 ; 0.3 MB, 0.3 MB
```

System Configuration Parameters:

```
startup= WIN.COM ; File referred to when starting
Windows
defdir= C:\WINDOWS ; Default directory for installation
short name= Windows ; Default based on [language]
welcome= "Windows 3.1" ; Welcome message
deflang= enu ; Default language based on
[codepage]
defxlat= 437 ; Default code page
defkeydll= usadll ; Default based on [keyboard.tables]
register= "regedit /s /u setup.reg" ; Default file for registration
database
tutor= "wintutor.exe" ; Tutorial to run at end of
installation
NetSetup= FALSE ; TRUE allows only SETUP /N
MouseDrv= TRUE ; Setup uses the mouse
Version= "3.1" ; Current Windows version
```

[disks] and [oemdisks] Sections

Define all installation disks and their properties.

Format:

```
disk_number= path, "disk_name", disk_tag
```

Field Definitions:

Field	Description
----	-----
disk_number	Single character 1-9 or A-Z (0 reserved for Setup directory)
path	Disk path ("." = same drive as Windows Setup disks)
disk_name	Disk label in quotes
disk_tag	Volume name for disk verification

Complete Standard Entries:

```
[disks]
1=. , "Microsoft Windows 3.1 Disk #1", disk1
2=. , "Microsoft Windows 3.1 Disk #2", disk2
3=. , "Microsoft Windows 3.1 Disk #3", disk3
4=. , "Microsoft Windows 3.1 Disk #4", disk4
5=. , "Microsoft Windows 3.1 Disk #5", disk5
6=. , "Microsoft Windows 3.1 Disk #6", disk6

[oemdisks]
Z=. , "HP DeskJet Series v2.0 disk (from printer box or contact HP)", diskz
```

[user] Section

Defines the temporary file containing user and company identification.

Core File Copying Sections

[windows] Section

Files copied to WINDOWS directory during MS-DOS Mode Setup.

Complete Standard Entries:

```
[windows]
1:setup.hlp
1:setup.inf
3:control.hlp
2:win.src, Net           ; Copied only for Administrative Setup (setup
/a)
1:system.src, Net       ; Copied only for Administrative Setup (setup
/a)
1:winhelp.exe
```

[windows.system] Section

Files copied to SYSTEM subdirectory.

Complete Standard Entries:

```
[windows.system]
1:gdi.exe
1:user.exe
1:win.cnf
1:lzexpand.dll
2:ver.dll
```

[windows.system.386] Section

386-specific files for SYSTEM subdirectory.

Complete Standard Entries:

```
[windows.system.386]
1:cpwin386.cpl
```

Memory Manager Support Sections

386Max Support:

```
[386max]  
2:386max.vxd ; Files copied if system is using 386Max  
2:windows.lod
```

BlueMax Support:

```
[bluemax]  
2:bluemax.vxd ; Files copied if system is using BlueMax  
2:windows.lod
```

[shell] Section

Defines the Windows shell application.

Complete Standard Entry:

```
[shell]  
progman.exe, "Windows Program Manager"
```

Display Driver Sections

Display Driver Components

Windows display drivers require three file types:

- **.DRV file** - Main display driver (e.g., VGA.DRV)
- **Grabber files** - .2GR for standard mode, .3GR for 386 enhanced mode
- **VDD files** - Virtual Display Drivers (VDDx.386) for 386 enhanced mode

[display] Section Format

```
keyname= driver, description, resolution, 286grabber, logo code, VDD,  
386grabber, ega.sys, logo data, optional section
```

Complete Field Definitions:

Field	Description
----	-----
keyname	Profile name for driver references in other SETUP.INF sections
driver	Filename of the display device driver

description	Driver description in quotes (appears in Change System Settings dialog)
resolution	Aspect ratio as three comma-separated numbers in quotes
286grabber	Filename of the 286 grabber for standard mode data exchange
logo code	Filename for Microsoft Windows logo code
VDD	Filename for the Virtual Display Driver
386grabber	Filename of the 386 grabber for 386 enhanced mode data exchange
ega.sys	Filename for data determining EGA.SYS driver installation need
logo data	Filename for appropriate Microsoft logo bitmap
optional section	Name of section with additional display driver information

Important: Do not change description strings as they are used for upgrade decisions.

Example Entry for 8514/a Display:

```
8514= 2:8514.drv, "8514/a", "100,120,120", 3:vgacolor.2gr, 2:vgalogo.lgo,
2:vdd8514.386, 3:vgadib.3gr, , 2:vgalogo.rle, 8514
```

Optional Display Sections

Available optional sections for display drivers:

```
[v7vga], [vgamono], [8514], [8514s], [tiga1], [tiga2], [v7b], [v7c], [v7d],
[v7t], [v7e], [xgasm], [xgalg], [xgalo]
```

Optional Section Format:

```
file, destination, ini file, section, OldEntry, NewEntry
```

Optional Section Field Definitions:

Field	Description
----	-----
file	Optional file to copy (can be null)
destination	Directory for file copy (0: = WINDOWS, 0:system = SYSTEM)
ini file	.INI file to modify (WIN.INI or SYSTEM.INI)
section	Section in .INI file to modify
OldEntry	Entry to remove from .INI file (in quotes, optional)
NewEntry	New entry to add to .INI file (in quotes)

Example Optional Section:

```
[8514]
, , system.ini, 8514.DRV, "dpi=", "dpi=120"
```

[.3gr] Font Sections

Define fonts for 386 grabbers that support text/graphics copying from non-Windows applications.

Available .3gr Sections:

```
[vga.3gr], [vgalo.3gr], [v7vga.3gr], [ega.3gr], [vgadib.3gr], [plasma.3gr],  
[herc.3gr], [tiga.3gr]
```

Example for Video 7 VGA:

```
[v7vga.3gr]  
2:CGA40WOA.FON,2:CGA40850.FON  
2:CGA80WOA.FON,2:CGA80850.FON  
2:EGA40WOA.FON,5:EGA40850.FON  
2:EGA80WOA.FON,2:EGA80850.FON
```

Font Selection Rules:

- Code page 437 (US default): Copies *WOA.FON files
- Other code pages: Copies *850.FON files

Keyboard and Code Page Sections

[keyboard.drivers] Section

Maps keyboard driver filenames to short names.

Complete Standard Entries:

```
[keyboard.drivers]  
kbd= 2:keyboard.drv  
kbdhp= 2:kbdhp.drv
```

[keyboard.types] Section

Creates keyboard short names used in [machine] section.

Format:

```
short_name = "description", DLL_filename
```

Field Definitions:

Field	Description
----	-----
short_name	Abbreviated descriptor for [machine] section
description	Description in quotes for Change System Settings dialog

DLL_filename	Supporting DLL filename (can be null)
--------------	---------------------------------------

Complete Standard Entries:

```
[keyboard.types]
t3s0alat= "All AT type keyboards (84-86 keys)",nodll
t1s2at&t= "AT&T '301' keyboard",nodll
t1s4at&t= "AT&T '302' keyboard",nodll
t4s0enha= "Enhanced 101 or 102 key US and Non US keyboards",nodll
t3s0hp1= "Hewlett-Packard Vectra keyboard (DIN)",nodll
t4s40oliv= "Olivetti 101/102 A keyboard",nodll
t1s0oliv= "Olivetti 83 key keyboard",nodll
t3s10oliv= "Olivetti 86 Key keyboard",nodll
t2s10oliv= "Olivetti M24 102 key keyboard",usadll
t1s42oliv= "PC-XT 83 key keyboard",nodll
t1s0pcxt= "PC/XT -Type keyboard (84 keys)",nodll
```

[keyboard.tables] Section

Maps DLL short names to disk locations for international language support.

Complete Standard Entries:

```
[keyboard.tables]
beldll= 2:kbdbe.dll , "Belgian"
bridll= 2:kbduk.dll , "British"
cafdll= 2:kbdfc.dll , "Canadian Multilingual"
dandll= 2:kbdca.dll , "Danish"
dutdll= 2:kbdne.dll , "Dutch"
findll= 2:kbdfi.dll, "Finnish"
fredll= 2:kbdfr.dll , "French"
candll= 2:kbdca.dll , "French Canadian"
gerdll= 2:kbdgr.dll , "German"
icedll= 2:kbdic.dll , "Icelandic"
itadll= 2:kbdit.dll , "Italian"
latdll= 2:kbdla.dll , "Latin American"
nordll= 2:kbdno.dll , "Norwegian"
pordll= 2:kbdpo.dll , "Portuguese"
spadll= 3:kbdsp.dll , "Spanish"
swedll= 2:kbdsw.dll , "Swedish"
swfdll= 2:kbdsf.dll , "Swiss French"
swgdll= 2:kbdsg.dll , "Swiss German"
nodll=, "US"
usadll= 2:kbdus.dll , "US"
usddll= 2:kbddv.dll , "US-Dvorak"
usxdll= 2:kbdusx.dll, "US-International"
```

[codepages] Section

Defines code page support for international systems.

Format:

```
codepage_number = xlat_table, OEMfont, WOAfont, "description"
```

Field Definitions:

Field	Description
----	-----
codepage_number	Table number for keyboard character mapping
xlat_table	Translation table filename for OEM font association
OEMfont	OEM font filename with disk number
WOAfont	Windows grabber font filename with disk number
description	Country description in quotes

Complete Standard Entries:

```
[codepages]  
863= 1:xlat863.bin, 2:vga863.fon, 2:app850.fon, "Canadian-French (863)"  
861= 2:xlat861.bin, 2:vga861.fon, 2:app850.fon, "Icelandic (861)"  
865= 2:xlat865.bin, 2:vga865.fon, 2:app850.fon, "Nordic (865)"  
850= 2:xlat850.bin, 2:vga850.fon, 2:app850.fon, "Multi-Lingual (850)"  
860= 3:xlat860.bin, 2:vga860.fon, 2:app850.fon, "Portuguese (860)"  
437= , , 2:dosapp.fon, "English (437)"
```

Mouse Driver Sections

[pointing.device] Section

Table of information for supported pointing devices.

Format:

```
keyname = mouse_driver, mouse_descriptor, VMD, optional_section
```

Field Definitions:

Field	Description
----	-----
keyname	Profile name
mouse_driver	Mouse driver filename with disk number
mouse_descriptor	Driver description in quotes for Setup dialog
VMD	Virtual Mouse Device support filename with disk number

optional_section	Section with additional mouse driver information
------------------	--------------------------------------------------

Special VMD Values:

- `x:*vmd`
 - File built into WIN386.EXE (not separate file)
- `x:`
 - Refers to disk where WIN386.EXE is located

Complete Standard Entries:

```
[pointing.device]
hpmouse= 2:hpmouse.drv, "HP Mouse (HP-HIL)", x:*vmd
lmouse= 3:lmouse.drv, "Logitech", 2:lvmd.386, lmouse
ps2mouse= 2:mouse.drv, "Microsoft, or IBM PS/2", x:*vmd
genius1= 2:microsoft.drv, "Genius serial mouse on COM1", 1:mscvmd.386
genius2= 2:microsoft.drv, "Genius serial mouse on COM2", 1:mscvmd.386
mssystem2= 2:microsoft.drv, "Mouse Systems serial or bus mouse", 1:mscvmd.386
mssystem1= 2:microsoft.drv, "Mouse Systems serial mouse on COM2", 1:mscvmd.386
nomouse= 2:nomouse.drv, "No mouse or other pointing device", x:*vmd
kbmouse= 2:kbmouse.drv, "Olivetti/AT&T Keyboard Mouse", x:*vmd
```

[dos.mouse.driver] Section

Maps Windows mouse drivers to MS-DOS mouse drivers.

Complete Standard Entries:

```
[dos.mouse.drivers]
mouse.sys= 4:mouse.SYS, "MS DOS Mouse driver .SYS ver 7.XX"
mouse.com= 4:mouse.com, "MS DOS Mouse driver .COM ver 7.XX"
mousehp.sys= 3:mousehp.SYS, "HP DOS Mouse driver .SYS ver 7.XX"
mousehp.com= 3:mousehp.com, "HP DOS Mouse driver .COM ver 7.XX"
```

[lmouse] Section

Support data for Logitech MS-DOS mouse driver.

Complete Standard Entry:

```
[lmouse]
2:lmouse.com,0:,,, ,
```

Network Installation Sections

[network] Section

Associates network keynames with installation files.

Format:

```
network_keyname = driver, description, HelpFile, optional_file,  
WininiSectName, SysiniSectName, VDD, ...
```

Field Definitions:

Field	Description
-----	-----
network_keyname	Profile for specific network driver
driver	Network driver filename with disk number
description	Driver description in quotes for Setup dialog
HelpFile	Associated help filename
optional_file	Optional file to install
WininiSectName	WIN.INI section to add/modify
SysiniSectName	SYSTEM.INI section to add/modify
VDD	Virtual Display Device support filenames

Complete Standard Entries:

```
[network]  
nonet= ,"No Network Installed"  
3open= ,"3Com 3+Open"  
3share= ,"3Com 3+Share" ,,,msnet_stuff  
lantastic= ,"Artisoft LANtastic"  
banyan= ,"Banyan Vines"  
dlr= ,"IBM OS/2 LAN Server"  
pclp= ,"IBM PC LAN Program"  
lanman= ,"Microsoft LAN Manager"  
msnet= ,"Microsoft Network (or 100% compatible)", ,,,msnet_stuff  
novell= ,"Novell Netware"  
pathworks= ,"DEC Pathworks"  
10net= ,"TCS 10Net"
```

[Network_Version] Sections

Provide version-specific network information.

Available Version Sections:

```
[10net.versions] ; TCS 10Net
[3open.versions] ; 3Com 3+Open
[banyan.versions] ; Banyan Vines
[dlr.versions] ; IBM OS/2 LAN Server
[lanman.versions] ; Microsoft LAN Manager
[lantastic.versions] ; Artisoft LANTastic
[novell.versions] ; Novell Netware
[pathworks.versions] ; DEC Pathworks
[pclp.versions] ; IBM PC LAN Program
```

Format:

```
version_number = "description", optional_files, optional_sections
```

Example for LAN Manager:

```
[lanman.versions]
xx000000="versions 1.X", , lmbasic
00020000="version 2.00 Basic", , lmbasic
01020000="version 2.00 Enhanced", , lmenh20
00021000="version 2.10 Basic", , lmbasic21
01021000="version 2.10 Enhanced", lanman21.drv, lmenh21 nodrv,lmenh21
```

[Network_Specific] Sections

Define INI file modifications for specific networks.

Available Network_Specific Sections:

```
[10net41], [10net41a], [10net42], [10net42def], [10net50]
[3open1]
[ban4], [ban41], [ban41def]
[dec4], [dec41]
[dlr12], [dlr12csd], [dlr13]
[lant1], [lant4], [lant4def]
[lmbasic], [lmbasic21], [lmenh20], [lmenh21], [lmenh21nodrv]
[msnet_stuff]
[novell301], [novell321]
[old_pclp], [pclp132]
[unsupported_net]
```

Format:

```
[network_keyname]
ini-keyname = section, entry_keyname, value
```

Example for Novell NetWare 3.01:

```
[novell301]
```

```
warning=2  
driver=2:netware.drv  
vxd=x:*vnetbios,2:vnetware.386,2:vipx.386  
sysdir=2:netware.hlp,2:nwpopup.exe  
windir=2:ipx.obj,2:ipxodi.com,2:netx.com,2:lsl.com  
windir=2:tbmi2.com
```

System Fonts Sections

[sysfonts] Section

System fonts by display resolution.

Complete Standard Entries:

```
[sysfonts]  
1:egasys.fon,"EGA (640x350) resolution System Font", "133,96,72"  
1:vgasys.fon,"VGA (640x480) resolution System Font", "100,96,96"  
1:8514sys.fon,"8514/a (1024x768) resolution System Font", "100,120,120"  
1:egasys.fon,"AT&T (640x400) resolution System Font", "120,96,80"
```

[fixedfonts] Section

Fixed-width system fonts by display resolution.

Complete Standard Entries:

```
[fixedfonts]  
2:egafix.fon,"EGA (640x350) resolution Fixed System Font", "133,96,72"  
1:vgafix.fon,"VGA (640x480) resolution Fixed System Font", "100,96,96"  
1:8514fix.fon,"8514/a (1024x768) resolution Fixed System Font",  
"100,120,120"  
2:egafix.fon,"AT&T (640x400) resolution Fixed System Font", "120,96,80"
```

[oemfonts] Section

Terminal fonts by display resolution.

Complete Standard Entries:

```
[oemfonts]  
1:egaoem.fon,"EGA (640x350) resolution Terminal Font (USA/Europe)",  
"133,96,72",1  
1:vgaoem.fon,"VGA (640x480) resolution Terminal Font (USA/Europe)",  
"100,96,96",1
```

```
1:8514oem.fon,"8514/a (1024x768) resolution Terminal Font (USA/Europe)",
"100,120,120",1
1:egaoem.fon,"AT&T (640x400) resolution Terminal Font
(USA/Europe)", "120,96,80",1
```

Program Manager Groups Sections

[new.groups] Section

Used when upgrading from Windows 3.0 to 3.1.

Format:

```
section = Progman_group, Min/Max
```

Field Definitions:

Field	Description
----	-----
section	Name of [group#] section with group definition
Progman_group	Profile name identifying group in Program Manager
Min/Max	1=maximize group, nothing=minimize group

Complete Standard Entries:

```
[new.groups]
group7=Main, 1
group1=Startup
group2=Accessories
group6=Games
```

[progman.groups] Section

Used for new Windows 3.1 installations.

Complete Standard Entries:

```
[progman.groups]
group3=Main, 1
group4=Accessories
group5=Games
group1=Startup
```

[group#] Sections

Define program items within Program Manager groups.

Format:

```
"description", filename.exe, icon_filename, icon_number, profile
```

Field Definitions:

Field	Description
-----	-----
description	Text below icon in Program Manager (in quotes)
filename.exe	Executable filename with extension
icon_filename	Icon extraction file (blank = first icon from filename.exe)
icon_number	Icon offset number (for 3rd icon, specify 2)
profile	If null, always added; otherwise only if installed via Add/Remove Files

Complete Group Definitions:

Main Group ([group3] for [progman.groups]):

```
[group3]
"File Manager", WINFILE.EXE
"Control Panel", CONTROL.EXE
"Print Manager", PRINTMAN.EXE
"Clipboard Viewer", CLIPBRD.EXE
"MS-DOS Prompt", DOSPRMPT.PIF, PROGMAN.EXE, 9
"Windows Setup", SETUP.EXE
"PIF Editor", PIFEDIT.EXE
"Read Me", README.WRI,, readme
```

Accessories Group ([group4] for [progman.groups]):

```
[group4]
"Write", WRITE.EXE,, write
"Paintbrush", PBRUSH.EXE,, pbrush
"Terminal", TERMINAL.EXE,, terminal
"Notepad", NOTEPAD.EXE,, notepad
"Recorder", RECORDER.EXE,, recorder
"Cardfile", CARDFILE.EXE,, cardfile
"Calendar", CALENDAR.EXE,, calendar
"Calculator", CALC.EXE,, calc
"Clock", CLOCK.EXE,, clock
"Object Packager", PACKAGER.EXE,, packager
"Character Map", CHARMAP.EXE,, charmap
"Media Player", MPLAYER.EXE,, mplayer
"Sound Recorder", SOUNDREC.EXE,, soundrec
```

Games Group ([group5] for [progman.groups]):

```
[group5]
"Solitaire", SOL.EXE,, sol
```

```
"Minesweeper", WINMINE.EXE,,, winmine
```

Additional Groups for [new.groups]:

```
[group1] ; For [progman.groups] and [new.groups]
[group2] ; For [new.groups]
"Object Packager", PACKAGER.EXE,,, packager
"Character Map", CHARMAP.EXE,,, charmap
"Media Player", MPLAYER.EXE,,, mplayer
"Sound Recorder", SOUNDREC.EXE,,, soundrec
"PIF Editor"
"Write", WRITE.EXE
"Control Panel"

[group6] ; For [new.groups]
"Solitaire", SOL.EXE,,, sol
"Minesweeper", WINMINE.EXE,,, winmine

[group7] ; For [new.groups]
"PIF Editor", PIFEDIT.EXE
"Read Me"
"Read Me", README.WRI,, readme
"Tutorial"
```

Fonts Sections

[fonts] Section

Raster and vector screen fonts based on display resolution.

Format:

```
filename, "description", "resolution"
```

Example VGA Entries:

```
[fonts]
(other entries)
6:SSERIFE.FON, "MS Sans Serif 8,10,12,14,18,24 (VGA res)", "100,96,96"
(other entries)
6:COURE.FON, "Courier 10,12,15 (VGA res)", "100,96,96"
(other entries)
6:SERIFE.FON, "MS Serif 8,10,12,14,18,24 (VGA res)", "100,96,96"
(other entries)
6:SYMBOLE.FON, "Symbol 8,10,12,14,18,24 (VGA res)", "100,96,96"
(other entries)
6:SMALLE.FON, "Small (VGA res)", "100,96,96"
```

[ttfonts] Section

TrueType font definitions.

Format:

```
font_header_file, "description", font_file, fontfamily_flags
```

Field Definitions:

Field	Description
----	-----
font_header_file	TrueType header source filename
description	Font description in quotes (first letter of each word capitalized)
font_file	TrueType font filename
fontfamily_flags	Font family name plus flag in quotes

Font Family Flags:

- 0000 = Normal weight font
- 0100 = Bold font
- 1000 = Italic font
- 1100 = Bold Italic font

Complete TrueType Entries:

```
[ttfonts]
S:ARIAL.FOT, "Arial (TrueType)", 5:arial.ttf, ""
S:ARIALBD.FOT, "Arial Bold (TrueType)", S:arialbd.ttf, "Arial0100"
S:ARIALBI.FOT, "Arial Bold Italic (TrueType)", 5:arialbi.ttf, "Arial1100"
S:ARIALI.FOT, "Arial Italic (TrueType)", 5:ariali.ttf, "Arial1000"
S:COUR.FOT, "Courier New (True Type)", 5:cour.ttf, ""
S:COURBD.FOT, "Courier New Bold (TrueType)", 5:courbd.ttf, "Courier0100"
S:COURBI.FOT, "Courier New Bold Italic (TrueType)", 5:courbi.ttf,
"Courier1100"
S:COURI.FOT, "Courier New Italic (TrueType)", 5:couri.ttf, "Courier1000"
3:TIMES.FOT, "Times New Roman (TrueType)", 4:times.ttf, ""
3:TIMESBD.FOT, "Times New Roman Bold (TrueType)", 4:timesbd.ttf, "Times New
Roman0100"
3:TIMESBI.FOT, "Times New Roman Bold Italic (TrueType)", 4:timesbi.ttf,
"Times New Roman1100"
4:TIMESI.FOT, "Times New Roman Italic (TrueType)", 4:timesi.ttf, "Times New
Roman1000"
S:SYMBOL.FOT, "Symbol (TrueType)", S:symbol.ttf, ""
```

Incompatible Driver Sections

Four sections for checking incompatible drivers and TSRs:

[compatibility] Section

Files listed here have their CONFIG.SYS commands removed during Setup.

[incompTSR1] Section

TSRs and drivers that prevent Setup from running. Must be removed from memory and AUTOEXEC.BAT/CONFIG.SYS before running Setup.

[incompTSR2] Section

TSRs and drivers that cause problems during Setup or when starting Windows.

[block_devices] Section

Block devices that are not compatible with Windows 3.1.

Miscellaneous Sections

[installable.drivers] Section

Multimedia driver specifications.

Format:

```
keyname= filename, types, description, VxDs, default_parameters
```

Complete Standard Entries:

```
[installable.drivers]
adlib= 3:adlib.drv,"MIDI","Ad Lib",4:vadlibd.386,
lapcl= 3:mpu401.drv,"MIDI","Roland LAPC1",,
midimapper= 4:midimap.drv,"MidiMapper","MIDI Mapper",,
mpu401= 3:mpu401.drv,"MIDI","Roland MPU401",,
sequencer= 4:mciseq.drv,"Sequencer","[MCI] MIDI Sequencer",,
soundblaster= 3:sndblst.drv,"Wave,MIDI","Creative Labs Sound Blaster
1.0",3:vsbd.386,,adlib
soundblaster2= 3:sndblst2.drv,"Wave,MIDI","Creative Labs Sound Blaster
1.5",3:vsbd.386,,adlib
timer= 5:timer.drv,"Timer","Timer",5:vtdapi.386,
thunder= 3:sndblst2.drv,"Wave,MIDI","Media Vision Thunder
Board",3:vsbd.386,,adlib
wave= 4:mciwave.drv,"WaveAudio","[MCI] Sound",,,,"4"
```

[translate] Section

OEM filename translations.

Example Entries:

```
[translate]
WinDiskName=25,"Microsoft Windows 3.0 Disk"
WinDiskName=14,"Windows Disk#"
*vddvga=2:vddvga30.386
ctil.lgo=2:herclogo.lgo
herclogo.rle=1:herclogo.rle
vddega=2:vddega.386
vgacolor.gr2=3:vgacolor.2gr
vgalogo.lgo=2:vgalogo.lgo
vgalogo.rle=2:vgalogo.rle
rgdi.lgo=2:vgalogo.lgo
rgdi.rle=2:vgalogo.rle
vga.gr3=1:vga30.3gr
```

[update.files] Section

Installable drivers to update if earlier versions are found.

Format:

```
location, filename
```

Location Values:

- 0: = WINDOWS directory
- 0:system = SYSTEM subdirectory

Complete Standard Entries:

```
[update.files]
0:system,3:sndblst.drv
0:system,3:sndblst2.drv
0:system,3:adlib.drv
0:system,3:mpu401.drv
0:system,5:vtdapi.386
0:system,3:vsbd.386
0:system,4:vadlibd.386
```

[Update.Dependents] Section

Updates files dependent on those listed in [Update.Files].

Complete Standard Entries:

```
[Update.Dependents]
msadlib.drv = 4:vadlibd.386
sndblst.drv = 4:vsbd.386
sndblst2.drv = 4:vsbd.386
```

[ini.upd.patches] Section

Temporary INI file profile renaming during Setup.

Format:

```
ini_file, section, temporary_profile, original_profile
```

Example Entries:

```
[ini.upd.patches]
system.ini, Boot, "olddrivers", "drivers"
win.ini, Desktop, "oldwallpaper", "wallpaper"
system.ini, Boot, "oldtaskman", "taskman.exe"
```

[blowaway] Section

Marks the end of installation information and start of configuration sections. Windows Mode Setup stops reading SETUP.INF here.

[ini.upd.31] Section

INI file updates for Windows 3.0 to 3.1 upgrade.

Format:

```
ini_file, section, OldEntry, NewEntry
```

Example Entries:

```
[ini.upd.31]
system.ini, 386Enh, "keyboard=*vkd"
system.ini, 386Enh, "device=*vpicd"
system.ini, 386Enh, "device=*blockdev"
system.ini, 386Enh, , "device=*pagefile"
win.ini, FontSubstitutes, , "Helv=MS Sans Serif"
win.ini, FontSubstitutes, , "Tms Rmn=MS Serif"
win.ini, FontSubstitutes, , "Courier=Courier New"
win.ini, FontSubstitutes, , "Times=Times New Roman"
```

```
win.ini, FontSubstitutes, , "Helvetica=Arial"
```

System Configuration Sections

[system] Section

Maps system short names to appropriate system files.

Complete Standard Entries:

```
[system]
system= 2:system.driv
sound= 1:mmsound.driv
comm= 1:comm.driv
hpsystem= 2:hpsystem.driv
```

[machine] Section

Installs appropriate system files for various machines.

Format:

```
keyname= description, system_driv, kbd_driv, kbd_type, mouse_driv, disp_driv,
sound_driv, comm_driv, himem_switch, ebios, Cookz
```

Complete Field Definitions:

Field	Description
-----	-----
keyname	Profile string for the system
description	System description in quotes for Setup dialog
system_driv	Short name for system driver from [system]
kbd_driv	Short name for keyboard driver from [keyboard.drivers]
kbd_type	Short name for keyboard type from [keyboard.types]
mouse_driv	Mouse driver keyname from [pointing.device]
disp_driv	Display driver keyname from [display]
sound_driv	Sound driver name from [system]
comm_driv	Communications driver name from [system]
himem_switch	A20 handler number (1-8) for HIMEM.SYS extended memory access
ebios	EBIOS support defined in [ebios]
Cookz	[Cookz] section with INI file modification information

Important: Do not change the order of entries in [machine] section.

Example Entries:

```
[machine]
ibm_compatible= "MS-DOS
System",system,kbd,t4s0enha,nomouse,egahires,sound,comm,,ebios,
ast_386_486= "AST: all 80386 and 80486 based
machines",system,kbd,t4s0enha,nomouse,egahires,sound,comm,,ebios,ast_cookz
at_and_t= "AT&T PC",system,kbd,t4s0enha,nomouse,vgahires,sound,comm,,ebios,
```

[Cookz] Sections

Hardware-specific INI file modifications.

Available Cookz Sections:

```
[apm_cookz], [apm_sl_cookz], [ast_cookz], [everex_cookz], [ibm140_cookz],
[ncr386sx_cookz], [nec_pm_cookz], [t5200_cookz], [zen386_cookz]
```

Format:

```
ini_file, section, cookie, needed_file
```

Example Entries:

```
[ast_cookz]
system.ini,386enh,"emmexclude=E000-EFFF",

[apm_cookz]
specialdriver,,5:power.drv
system.ini,386enh,"device=vpowrd.386",5:vpowrd.386
,,5:power.hlp
```

[special_adapter] Section

Support for special adapters requiring additional files.

Complete Standard Entries:

```
[special_adapter]
etherlink= DMAbuffersize,32 ; Needed if EtherLink MC is detected
cdrom= 2:lanman10.386 ; Needed for CD ROM extensions
```

[ebios] Section

Extended BIOS support files.

Complete Standard Entries:

```
[ebios]
```

```
ebios= x:*ebios ; Required for most 386 machines  
hpebios= 2:hpebios.386,x:*ebios ; Required for HP 386 machines
```

[language] Section

Language support libraries.

Format:

```
keyname= language_DLL, DLL_description, language_ID
```

Complete Standard Entries:

```
[language]  
dan= 2:langsca.dll, "Danish", 1030  
nld= 2:langdut.dll, "Dutch", 1043  
enu=, "English (American)", 1033  
eng= 2:langeng.dll, "English (International)", 2057  
fin= 2:langsca.dll, "Finnish", 1035  
fra= 2:langfrn.dll, "French", 1036  
frc= 2:langeng.dll, "French Canadian", 3084  
deu= 2:langger.dll, "German", 1031  
isl= 2:langsca.dll, "Icelandic", 1039  
ita= 2:langeng.dll, "Italian", 1040  
nor= 2:langsca.dll, "Norwegian", 1044  
ptg= 2:langeng.dll, "Portuguese", 2070  
esp= 2:langspa.dll, "Spanish (Classic)", 1034  
esn= 2:langeng.dll, "Spanish (Modern)", 3082  
sve= 2:langsca.dll, "Swedish", 1053
```

File Copying Mechanism Details

The SETUP.INF file copying system operates through these key mechanisms:

From:

<http://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:

<http://ftp.osfree.org/doku/doku.php?id=en:docs:win16:applications:setup&rev=1761113125>

Last update: **2025/10/22 06:05**

