



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=1CH

Version

1 and higher

Brief

GET ALLOCATION INFORMATION FOR SPECIFIC DRIVE

Family API

none

Input

```
AH = 1Ch
DL = drive (00h = default, 01h = A:, etc)
```

Return

AL = sectors per cluster (allocation unit), or FFh if invalid drive

```
CX = bytes per sector
DX = total number of clusters
DS:BX -> media ID byte (see #01356)
```

Notes

```
under DOS 1.x, DS:BX points at an actual copy of the FAT; later
versions return a pointer to a copy of the FAT's ID byte
on a DBLSPACE drive, the total number of clusters is based on the
```

estimated compression ratio
 this function may not be properly supported on CD-ROMs and other installable file systems (use AX=4402h"CD-ROM" for CD-ROMs instead)

BUG: DOS 7.10 (Win95B/Win98) reportedly returns incorrect values in AL and

DX for FAT12/FAT16 drives, even though it manages correct results for FAT32 drives (DOS windows are not affected, only real-mode DOS)

See also

AH=1Bh,AH=36h

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H , INT 21H : 00H , 25H , 26H , 31H , 34H , 35H , 4BH , 4CH , 4DH , 50H , 51H , 52H , 55H , 62H , INT 22H , INT 27H , INT 28H
File manager	INT 25H , INT 26H , INT 21H : 0DH , 0EH , 0FH , 10H , 11H , 12H , 13H , 14H , 15H , 16H , 17H , 19H , 1AH , 1BH , 1CH , 21H , 22H , 23H , 24H , 27H , 28H , 29H , 2EH , 2FH , 32H , 3305H , 36H , 39H , 3AH , 3BH , 3CH , 3DH , 3EH , 3FH , 40H , 41H , 42H , 4300H , 4301H , 45H , 45H , 46H , 4EH , 4FH , 54H , 56H , 5700H , 5701H , 5AH , 5BH , 5c00H , 5c01H , 60H , 67H , 68H , 6900H , 6901H , 6AH , 6CH
Character Device I/O	INT 29H , INT 21H : 01H , 02H , 03H , 04H , 05H , 06H , 07H , 08H , 09H , 0AH , 0BH , 0AH , 0CH , 5D07H , 5D08H , 5D09H , 5D0AH
Signals	INT 23H , INT 24H , INT 21H : 3300H , 3301H , 3302H
Memory manager	INT 21H : 48H , 49H , 4AH , 5800H , 5801H , 5802H , 5803H
Date and Time	INT 21H : 2AH , 2BH , 2CH , 2DH
Misc	INT 21H : 30H , 3306H , 3700H , 3701H , 3702H , 3703H , 59H
NLS	INT 21H : 3303H , 3304H , 3800H , 3801H , 6300H , 6301H , 6301H , 6500H , 6501H , 6502H , 6503H , 6504H , 6505H , 6506H , 6507H , 6520H , 6521H , 6522H , 6523H , 65A0H , 65A1H , 65A2H , 6601H , 6602H
Devices	INT 21H : 4400H , 4401H , 4402H , 4403H , 4404H , 4405H , 4406H , 4407H , 4408H , 4409H , 440AH , 440BH , 440CH , 440DH , 440EH , 440FH , 4410H , 4411H , 53H
Network	INT 21H : 5E00H , 5E01H , 5E02H , 5E03H , 5E04H , 5E05H , 5F00H , 5F01H , 5F02H , 5F03H , 5F04H , 5F05H , 5F07H , 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize

osFree Macro Library	
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOctl DosDevIOctl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:

<https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://ftp.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:1c&rev=1607417206>Last update: **2020/12/08 08:46**