



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=3DH

Version

2 and higher

Brief

“OPEN” - OPEN EXISTING FILE

Family API

Input

```
AH = 3Dh
AL = access and sharing modes (see #01402)
DS:DX -> ASCIZ filename
CL = attribute mask of files to look for (server call only)
```

Return

CF clear if successful

```
AX = file handle
CF set on error
AX = error code (01h,02h,03h,04h,05h,0Ch,56h) (see #01680 at
AH=59h)
```

Notes

Notes: file pointer is set to start of file

```

if SHARE or a network is loaded, the file open may fail if the file
  is already open, depending on the combination of sharing modes
  (see #01403,#01404)
file handles which are inherited from a parent also inherit sharing
  and access restrictions
files may be opened even if given the hidden or system attributes
  under the FlashTek X-32 DOS extender, the pointer is in DS:EDX
DR DOS checks the system password or explicitly supplied password at
  the end of the filename (following a semicolon) against the reserved
  field in the directory entry before allowing access
sharing modes are only effective on local drives if SHARE is loaded

```

BUG: Novell DOS 7 SHARE v1.00 would refuse file access in the cases in

```

#01403 marked with [1] (read-only open of a read-only file
  which had previously been opened in compatibility mode); this was
  fixed in SHARE v1.01 of 09/29/94

```

Bitfields for access and sharing modes: Bit(s) Description (Table 01402) 2-0 access mode

```

000 read only
001 write only
010 read/write
011 (DOS 5+ internal) passed to redirector on EXEC to allow
  case-sensitive filenames

```

3 reserved (0) 6-4 sharing mode (DOS 3.0+) (see #01403)

```

000 compatibility mode
001 "DENYALL" prohibit both read and write access by others
010 "DENYWRITE" prohibit write access by others
011 "DENYREAD" prohibit read access by others
100 "DENYNONE" allow full access by others
111 network FCB (only available during server call)

```

7 inheritance

```

if set, file is private to current process and will not be inherited
  by child processes

```

(Table 01403) Values of DOS 2-6.22 file sharing behavior:

| | |
|--|-----------------------------|
| | Second and subsequent Opens |
|--|-----------------------------|

First |Compat Deny Deny Deny Deny Open | All Write Read None

| |
|------------------------------------|
| R W RW R W RW R W RW R W RW R W RW |
|------------------------------------|

| |
|---|
| ----- ----- Compat R Y Y N N N 1 N N N N 1 N N |
|---|

```

W |Y Y Y N N N N N N N N N N
RW|Y Y Y N N N N N N N N N N

```

-----| Deny R |C C C N N N N N N N N N N N N All W |C C C N N N N N N N N N N N N

```

RW|C C C N N N N N N N N N N

```

-----| Deny R |2 C C N N N Y N N N N N Y N N Write W |C C C N N N N N N Y N N Y N N

```

RW|C C C N N N N N N N N N Y N N

```

-----| Deny R |C C C N N N N Y N N N N N Y N Read W |C C C N N N N N N Y N N Y N

```

RW|C C C N N N N N N N N N Y N

```

-----| Deny R |2 C C N N N Y Y Y N N N Y Y Y None W |C C C N N N N N N Y Y Y Y Y Y

```

RW|C C C N N N N N N N N N Y Y Y

```

Legend: Y = open succeeds, N = open fails with error code 05h

```

C = open fails, INT 24 generated
1 = open succeeds if file read-only, else fails with error code
2 = open succeeds if file read-only, else fails with INT 24

```

(Table 01404) Values for DOS 7.x file sharing behavior:

| Second and subsequent Opens

First |Compat Deny Deny Deny Deny Open | All Write Read None

```

|R W RW A R W RW A R W RW A R W RW A R W RW A

```

-----| ----- Compat R |Y Y Y Y N N N N Y N N Y N N N Y Y N N Y

```

W |Y Y Y C N N N N N N N N N N Y Y N N Y
RW|Y Y Y C N N N N N N N N N N Y Y N N Y
NA|Y C C Y N N N N Y N N Y N N N Y Y N N Y

```

-----| Deny R |C C C C N N N N N N N N N N N N N N All W |C C C C N N N N N N N N N N N N N N N N

```

RW|C C C C N N N N N N N N N N N N N N
NA|C C C C N N N N N N N N N N N N N N

```

-----| Deny R |Y C C Y N N N N Y N N Y N N N Y N N Y Write W |C C C C N N N N N N N Y N N Y N N Y

```

RW|C C C C N N N N N N N N N Y Y N N Y

```

NA|Y C C Y N N N N Y N N Y N N N Y Y N N Y

----| Deny R |C C C C N N N N Y N N N N N N Y N N Read W |C C C C N N N N N N N N Y N N N
Y N N

RW|C C C C N N N N N N N N N N N N N Y N N
NA|Y Y Y Y N N N N Y Y Y Y N N N Y Y Y Y Y

----| Deny R |Y Y Y Y N N N N Y Y Y Y N N N Y Y Y Y None W |C C C C N N N N N N N Y Y Y Y Y Y
Y

RW|C C C C N N N N N N N N N N N Y Y Y Y Y
NA|Y Y Y Y N N N N Y Y Y Y N N N Y Y Y Y Y

Legend: R → reading, W → writing, RW → both reading & writing,

A/NA -> reading without access time update
Y = open succeeds, N = open fails with error code 05h
C = open fails, INT 24 generated

See also

AH=0Fh,AH=3Ch,AX=4301h,AX=5D00h,INT 2F/AX=1116h,INT 2F/AX=1226h

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

| DOS API | |
|----------------------|---|
| Process manager | INT 20H , INT 21H : 00H , 25H , 26H , 31H , 34H , 35H , 4BH , 4CH , 4DH , 50H , 51H , 52H , 55H , 62H , INT 22H , INT 27H , INT 28H |
| File manager | INT 25H , INT 26H , INT 21H : 0DH , 0EH , 0FH , 10H , 11H , 12H , 13H , 14H , 15H , 16H , 17H , 19H , 1AH , 1BH , 1CH , 21H , 22H , 23H , 24H , 27H , 28H , 29H , 2EH , 2FH , 32H , 3305H , 36H , 39H , 3AH , 3BH , 3CH , 3DH , 3EH , 3FH , 40H , 41H , 42H , 4300H , 4301H , 45H , 45H , 46H , 4EH , 4FH , 54H , 56H , 5700H , 5701H , 5AH , 5BH , 5c00H , 5c01H , 60H , 67H , 68H , 6900H , 6901H , 6AH , 6CH |
| Character Device I/O | INT 29H , INT 21H : 01H , 02H , 03H , 04H , 05H , 06H , 07H , 08H , 09H , 0AH , 0BH , 0AH , 0CH , 5D07H , 5D08H , 5D09H , 5D0AH |
| Signals | INT 23H , INT 24H , INT 21H : 3300H , 3301H , 3302H |
| Memory manager | INT 21H : 48H , 49H , 4AH , 5800H , 5801H , 5802H , 5803H |
| Date and Time | INT 21H : 2AH , 2BH , 2CH , 2DH |
| Misc | INT 21H : 30H , 3306H , 3700H , 3701H , 3702H , 3703H , 59H |
| NLS | INT 21H : 3303H , 3304H , 3800H , 3801H , 6300H , 6301H , 6301H , 6500H , 6501H , 6502H , 6503H , 6504H , 6505H , 6506H , 6507H , 6520H , 6521H , 6522H , 6523H , 65A0H , 65A1H , 65A2H , 6601H , 6602H |

| DOS API | |
|-----------------------------|--|
| Devices | INT 21H: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H |
| Network | INT 21H: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H |
| osFree Macro Library | |
| Video I/O | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @CIs |
| Hardware info | @Equipment @MemSize |
| Serial I/O | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus |
| Tape I/O | @TapeOn @TapeOff @TapeRead @TapeWrite |
| Keyboard I/O | @KbdStatus @CharIn @CharPeek |
| Printer I/O | @PrnPrint @PrnInit @PrnStatus |
| Disk I/O | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat |
| Date and Time | @SetTime @GetTime |
| Mouse | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion |
| Memory manager | @ModBlok SET_BLOCK |

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

| Family API | | |
|-------------------|-----------------|--|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOCtl DosDevIOCtl2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| KBD | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| | KBD | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |
| | VIO | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |
| | Tools | BIND |
| | Modules | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL |
| | Libraries | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB |

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:

<https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://ftp.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:3d&rev=1619753430>

Last update: **2021/04/30 03:30**

