



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=4DH

Version

2 and higher

Brief

GET RETURN CODE (ERRORLEVEL)

Family API

Input

AH = 4Dh

Return

```
AH = termination type
  00h normal (INT 20,INT 21/AH=00h, or INT 21/AH=4Ch)
  01h control-C abort
  02h critical error abort
  03h terminate and stay resident (INT 21/AH=31h or INT 27)
```

AL = return code

CF clear

Notes

the word in which DOS stores the return code is cleared after being read by this function, so the return code can only be retrieved once

COMMAND.COM stores the return code of the last external command it executed as ERRORLEVEL

this call should not be used if the child was started with AX=4B04h; use AH=8Ah instead

the following sequence will close a Virtual DOS Machine under OS/2 2.0 through OS/2 Merlin (but may change in the future):

```
MOV AH,4Dh  
INT 21h  
HLT  
DB 02h,0FDh
```

This sequence is the only way to close a specific VDM which was booted from floppy or a disk image.

See also

[AH=4Bh,AH=4Ch](#)

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H , INT 21H : 00H , 25H , 26H , 31H , 34H , 35H , 4BH , 4CH , 4DH , 50H , 51H , 52H , 55H , 62H , INT 22H , INT 27H , INT 28H
File manager	INT 25H , INT 26H , INT 21H : 0DH , 0EH , 0FH , 10H , 11H , 12H , 13H , 14H , 15H , 16H , 17H , 19H , 1AH , 1BH , 1CH , 21H , 22H , 23H , 24H , 27H , 28H , 29H , 2EH , 2FH , 32H , 3305H , 36H , 39H , 3AH , 3BH , 3CH , 3DH , 3EH , 3FH , 40H , 41H , 42H , 4300H , 4301H , 45H , 45H , 46H , 4EH , 4FH , 54H , 56H , 5700H , 5701H , 5AH , 5BH , 5c00H , 5c01H , 60H , 67H , 68H , 6900H , 6901H , 6AH , 6CH
Character Device I/O	INT 29H , INT 21H : 01H , 02H , 03H , 04H , 05H , 06H , 07H , 08H , 09H , 0AH , 0BH , 0AH , 0CH , 5D07H , 5D08H , 5D09H , 5D0AH
Signals	INT 23H , INT 24H , INT 21H : 3300H , 3301H , 3302H
Memory manager	INT 21H : 48H , 49H , 4AH , 5800H , 5801H , 5802H , 5803H
Date and Time	INT 21H : 2AH , 2BH , 2CH , 2DH
Misc	INT 21H : 30H , 3306H , 3700H , 3701H , 3702H , 3703H , 59H
NLS	INT 21H : 3303H , 3304H , 3800H , 3801H , 6300H , 6301H , 6301H , 6500H , 6501H , 6502H , 6503H , 6504H , 6505H , 6506H , 6507H , 6520H , 6521H , 6522H , 6523H , 65A0H , 65A1H , 65A2H , 6601H , 6602H
Devices	INT 21H : 4400H , 4401H , 4402H , 4403H , 4404H , 4405H , 4406H , 4407H , 4408H , 4409H , 440AH , 440BH , 440CH , 440DH , 440EH , 440FH , 4410H , 4411H , 53H
Network	INT 21H : 5E00H , 5E01H , 5E02H , 5E03H , 5E04H , 5E05H , 5F00H , 5F01H , 5F02H , 5F03H , 5F04H , 5F05H , 5F07H , 5F08H
osFree Macro Library	

osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:4d&rev=1714702658>

Last update: **2024/05/03 02:17**

