

FSH_SETVOLUME

Purpose

This function provides the mechanism for assuring that a desired volume is in a removable media drive before I/O is done to the drive.

Calling Sequence

```
int far pascal FSH_SETVOLUME(hVPB , fControl)

unsigned short hVPB;
unsigned short fControl;
```

Where

hVPB is the volume handle for the source of I/O.

fControl is the bit mask of pop-up control actions:

Bit 0 off	indicates volume change pop-up desired
Bit 0 on	indicates no volume change pop-up
All other bits are reserved and must be zero.	

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

- `ERROR_VOLUME_CHANGED` - is an indication that removable media volume change has occurred.
- `ERROR_INVALID_PARAMETER` - the *fControl* flag word has reserved bits on.

Remarks

This routine is used by the *FSH_CALLDRIVER* routine to insure that the desired volume is in a removable media drive. FSDs can use it for the same purpose.

FSH_SETVOLUME may block.

Note: OS/2 does not validate input parameters. An FSD, therefore, should call *FSH_PROBEBUF* where appropriate.

From:
<https://osfree.org/doku/> - **osFree wiki**

Permanent link:
<https://osfree.org/doku/doku.php?id=en:ibm:ifs:helpers:setvol>

Last update: **2014/05/13 07:49**



