

## MouGetDevStatus

**Bindings:** C, MASM

This call returns status flags for the installed mouse device driver.

*MouGetDevStatus* (DeviceStatus, DeviceHandle)

*DeviceStatus* (**PUSHORT**) - output Address of the current status flag settings for the installed mouse device driver.

The return value is a 2-byte set of bit flags.

Bit	Description
15-10	Reserved, set to zero.
9	Set if mouse data returned in mickeys, not pels.
8	Set if the drawing operations for pointer draw routine are disabled.
7-4	Reserved, set to zero.
3	Set if pointer draw routine disabled by unsupported mode.
2	Set if flush in progress.
1	Set if block read in progress.
0	Set if event queue busy with I/O.

*DeviceHandle* (**HMOU**) - input Mouse device handle from a previous [MouOpen](#).

*rc* (**USHORT**) - return Return code descriptions are:

0	NO_ERROR
385	ERROR_MOUSE_NO_DEVICE
466	ERROR_MOU_DETACHED
501	ERROR_MOUSE_NO_CONSOLE
505	ERROR_MOU_EXTENDED_SG

From:

<https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://ftp.osfree.org/doku/doku.php?id=en:ibm:prcp:mou:getdevstatus&rev=1454561294>

Last update: **2016/02/04 04:48**

