

## MouGetPtrShape

**Bindings:** C, MASM

This call allows a process to get (copy) the pointer shape for the session.

*MouGetPtrShape* (PtrBuffer, PtrDefRec, DeviceHandle)

*PtrBuffer* (**PBYTE**) - output Address of an area in application storage where the pointer draw device driver returns the pointer bit image. See *MouSetPtrShape* for a further description of the resulting content of this buffer.

*PtrDefRec* (**PPTRSHAPE**) - input/output Address of a structure in application storage where the application stores the data necessary for the pointer device driver to return information about the Row by Col image for each bit plane for the mode the display is currently running. See *MouSetPtrShape* for a further description of the contents of this structure.

*TotLength* (**USHORT**) Length of the pointer buffer available for the pointer device driver to build a Row by Col image for each bit plane for the mode the display is currently running. This value is supplied by the application. If the value is too small, pointer draw places the true length of the image in this field, and returns an error.

For all OS/2 system-supported modes, *TotLength* is specified in bytes and is equal to:

**Mono & Text Modes** For text mode height and width must be 1, so length is always 4.

```
//TotLength// = (height in chars) * (width in chars) * 2 * 2
               = 1 * 1 * 2 * 2
               = 4
```

**Graphics Mode** Width-in-pels must be a multiple of 8.

```
//TotLength// = (height in pels)*(width in pels)*(bits per pel)*2/8
```

### Modes 4 and 5 (320 X 200)

$TotLength = (\text{height}) * (\text{width}) * 2 * 2 / 8$

### Mode 6 (640 X 200)

$TotLength = (\text{height}) * (\text{width}) * 1 * 2 / 8$

Length calculations produce byte boundary buffer sizes.

*col* (**USHORT**) Number of columns in the mouse shape. In graphics modes, this field contains the pel width (columns) of the mouse shape for the session and must be greater than or equal to 1. In text modes, *col* must equal 1.

*row* (**USHORT**) Number of rows in the mouse shape. In graphics modes, this field contains the pel height (rows) of the mouse shape for the session and must be greater than or equal to 1. In text modes, *row* must equal 1.

**coloffset (USHORT)** This value is returned by the mouse device driver to indicate the relative column offset within the pointer image. The value defines the center (hotspot) of the pointer image. This value is a signed number that represents either character or pel offset, depending on the display mode.

**rowoffset (USHORT)** This value is returned by the mouse device driver to indicate the relative row offset within the pointer image. The value defines the center (hotspot) of the pointer image. This value is a signed number that represents either character or pel offset, depending on the display mode.

**DeviceHandle (HMOU)** - input Handle of the mouse device from a previous MouOpen.

**rc (USHORT)** - return Return code descriptions are:

|     |                        |
|-----|------------------------|
| 0   | NO_ERROR               |
| 385 | ERROR_MOUSE_NO_DEVICE  |
| 387 | ERROR_MOUSE_INV_PARMS  |
| 466 | ERROR_MOU_DETACHED     |
| 501 | ERROR_MOUSE_NO_CONSOLE |
| 505 | ERROR_MOU_EXTENDED_SG  |

## Remarks

The application passes a parameter list with the same meaning as defined for [MouSetPtrShape](#) to the mouse device driver. The mouse device driver copies the parameters that describe the pointer shape and attributes into the pointer definition control block pointed to by the *PtrDefRec* parameter. The word 0 (buffer length = *TotLength*) pointer definition record parameter field must contain the size in bytes of the application buffer where the device driver is to insert the sessions pointer image. All other words in the parameter list are returned to the application by [MouGetPtrShape](#).

If the buffer size is insufficient, the *TotLength* field contains the actual size in bytes of the returned pointer image.

The pointer shape may be set by the application with [MouSetPtrShape](#) or may be the default image provided by the installed Pointer Device Driver.

## C bindings

```
typedef struct _PTRSHAPE { /* moups */
    USHORT cb; /* total length necessary to build image */
    USHORT col; /* # of columns in mouse shape */
    USHORT row; /* number of rows in mouse shape */
    USHORT colHot; /* column coordinate of pointer image
                    hotspot */
    USHORT rowHot; /* row coordinate of pointer image
                    hotspot */
} PTRSHAPE;

#define INCL_MOU
```

```

USHORT  rc = MouGetPtrShape(PtrBuffer, PtrDefRec, DeviceHandle);

PBYTE   PtrBuffer;      /* Pointer shape buffer */
PPTRSHAPE PtrDefRec;    /* Pointer definition struct */
HMOU    DeviceHandle;   /* Mouse device handle */

USHORT  rc;              /* return code */

```

## MASM bindings

```

PTRSHAPE struc
  mousps_cb      dw  ? ;total length necessary to build image
  mousps_col     dw  ? ;# of columns in mouse shape
  mousps_row     dw  ? ;number of rows in mouse shape
  mousps_colHot  dw  ? ;column coordinate of pointer image hotspot
  mousps_rowHot  dw  ? ;row coordinate of pointer image hotspot
PTRSHAPE ends

EXTRN  MouGetPtrShape:FAR
INCL_MOU      EQU 1

PUSH@  OTHER  PtrBuffer      ;Pointer shape buffer
PUSH@  OTHER  PtrDefRec     ;Pointer definition struct
PUSH   WORD   DeviceHandle   ;Mouse device handle
CALL   MouGetPtrShape

Returns  WORD

```

From:  
<https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:  
<https://ftp.osfree.org/doku/doku.php?id=en:ibm:prcp:mou:getptrshape>

Last update: **2016/09/15 04:03**

