

Note: This API call is for DOS and Win16 personality only. Use Family API for portability.

2018/09/07 05:04 · prokushev · 0 Comments

Int 21H, AH=5FH, AL=02H

Version

3.1 and higher

Brief

GET REDIRECTION LIST ENTRY

Family API

Input

```
  AX = 5F02h
 BX = zero-based redirection list index
 CX = driver signature
   0000h LANtastic
   4E57h ('NW') NetWare
 DS:SI -> 16-byte buffer for ASCIZ local device name or drive letter
followed by colon
 ES:DI -> 128-byte buffer for ASCIZ network name
```

Return

```
CF clear if successful
BH = device status
  00h valid
  01h invalid
  02h valid (connected from inside Windows for Workgroups v3.11)
BL = device type
  03h printer
  04h disk drive
CX = user data previously set with AX=5F03h
```

```
DS:SI and ES:DI buffers filled
DX,BP destroyed
CF set on error
  AX = error code (01h,12h) (see #01680 at AH=59h/BX=0000h)
```

Macro

Notes

This function is passed through to INT 2F/AX=111Eh by the DOS kernel. Error code 12h is returned if BX is greater than the size of the list. Also supported by Banyan VINES, PC-NFS, LANtastic, and 10NET. Supported by LapLink RemoteAccess but returns the local drive letter; the remote drive letter can be obtained with INT 2F/AX=Cxxxh (see INT 2F/AX=C000h“LapLink”). The returned device name may or may not include a colon, depending on the network software

See also

AX=5F03h - INT 2F/AX=111Eh

Note

Text based on Ralf Brown Interrupt List Release 61

DOS API	
Process manager	INT 20H, **INT 21H**: 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, **INT 21H**: 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, **INT 21H**: 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, **INT 21H**: 3300H, 3301H, 3302H
Memory manager	**INT 21H**: 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	**INT 21H**: 2AH, 2BH, 2CH, 2DH
Misc	**INT 21H**: 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	**INT 21H**: 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H
Devices	**INT 21H**: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H

DOS API	
Network	**INT 21H**: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments
2018/09/04 17:23 · prokushev · 0 Comments

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
http://www.osfree.org/doku/ - **osFree wiki**

Permanent link:
http://www.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:5f:02

Last update: **2024/05/06 04:03**