 This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · 0 Comments
2021/08/20 03:18 · prokushev · 0 Comments

MouGetPtrShape

This call allows a process to get (copy) the pointer shape for the session.

Syntax

```
MouGetPtrShape (PtrBuffer, PtrDefRec, DeviceHandle)
```

Parameters

- PtrBuffer (PBYTE) - output: Address of an area in application storage where the pointer draw device driver returns the pointer bit image. See MouSetPtrShape for a further description of the resulting content of this buffer.
- PtrDefRec (PPTRSHAPE) - input/output: Address of a structure in application storage where the application stores the data necessary for the pointer device driver to return information about the Row by Col image for each bit plane for the mode the display is currently running. See MouSetPtrShape for a further description of the contents of this structure.
    - TotLength (USHORT) : Length of the pointer buffer available for the pointer device driver to build a Row by Col image for each bit plane for the mode the display is currently running. This value is supplied by the application. If the value is too small, pointer draw places the true length of the image in this field, and returns an error.
    - col (USHORT)

Number of columns in the mouse shape. In graphics modes, this field contains the pel width (columns) of the mouse shape for the session and must be greater than or equal to 1. In text modes, col must equal 1.

- row (USHORT)

Number of rows in the mouse shape. In graphics modes, this field contains the pel height (rows) of the mouse shape for the session and must be greater than or equal to 1. In text modes, row must equal 1.

- coloffset (USHORT)

This value is returned by the mouse device driver to indicate the relative column offset within the pointer image. The value defines the center (hotspot) of the pointer image. This value is a signed number that represents either character or pel offset, depending on the display mode.

- rowoffset (USHORT)

This value is returned by the mouse device driver to indicate the relative row offset within the pointer image. The value defines the center (hotspot) of the pointer image. This value is a signed number that represents either character or pel offset, depending on the display mode.

- DeviceHandle (HMOU) - input:Handle of the mouse device from a previous MouOpen.

For all OS/2 system-supported modes, TotLength is specified in bytes and is equal to:

- Mono & Text Modes
  - For text mode height and width must be 1, so length is always 4.

```
TotLength = (height in chars) * (width in chars) * 2 * 2
          = 1 * 1 * 2 * 2
          = 4
```

- Graphics Mode
  - Width-in-pels must be a multiple of 8.
  - TotLength = (height in pels)*(width in pels)*(bits per pel)*2/8
- Modes 4 and 5 (320 X 200)
  - TotLength = (height) * (width) * 2 * 2 / 8
- Mode 6 (640 X 200)
- TotLength = (height) * (width) * 1 * 2 / 8

Length calculations produce byte boundary buffer sizes.

Return Code

rc (USHORT) - return

Return code descriptions are:

- 0 NO_ERROR
- 385 ERROR_MOUSE_NO_DEVICE
- 387 ERROR_MOUSE_INV_PARMS
- 466 ERROR_MOU_DETACHED
- 501 ERROR_MOUSE_NO_CONSOLE
- 505 ERROR_MOU_EXTENDED_SG

Remarks

The application passes a parameter list with the same meaning as defined for MouSetPtrShape to the mouse device driver. The mouse device driver copies the parameters that describe the pointer shape and attributes into the pointer definition control block pointed to by the PtrDefRec parameter. The word 0 (buffer length = TotLength) pointer definition record parameter field must contain the size in bytes of the application buffer where the device driver is to insert the sessions pointer image. All other words in the parameter list are returned to the application by MouGetPtrShape.

If the buffer size is insufficient, the TotLength field contains the actual size in bytes of the returned pointer image.

The pointer shape may be set by the application with MouSetPtrShape or may be the default image provided by the installed Pointer Device Driver.

Bindings

C

```
typedef struct _PTRSHAPE {  /* moups */
  USHORT cb;                /* total length necessary to build image */
  USHORT col;               /* # of columns in mouse shape */
  USHORT row;               /* number of rows in mouse shape */
  USHORT colHot;            /* column coordinate of pointer image hotspot */
  USHORT rowHot;            /* row coordinate of pointer image hotspot */
} PTRSHAPE;

#define INCL_MOU

USHORT  rc = MouGetPtrShape(PtrBuffer, PtrDefRec, DeviceHandle);

PBYTE       PtrBuffer;     /* Pointer shape buffer */
PPTRSHAPE   PtrDefRec;     /* Pointer definition struct */
HMOU        DeviceHandle;  /* Mouse device handle */

USHORT      rc;            /* return code */
```

MASM

```
PTRSHAPE struc
  moups_cb      dw  ? ;total length necessary to build image
  moups_col     dw  ? ;# of columns in mouse shape
  moups_row     dw  ? ;number of rows in mouse shape
  moups_colHot  dw  ? ;column coordinate of pointer image hotspot
  moups_rowHot  dw  ? ;row coordinate of pointer image hotspot
PTRSHAPE ends

EXTRN  MouGetPtrShape:FAR
INCL_MOU            EQU 1

PUSH@  OTHER   PtrBuffer     ;Pointer shape buffer
PUSH@  OTHER   PtrDefRec     ;Pointer definition struct
PUSH   WORD    DeviceHandle  ;Mouse device handle
CALL   MouGetPtrShape
```

```
Returns WORD
```

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
http://osfree.org/doku/ - **osFree wiki**

Permanent link:
http://osfree.org/doku/doku.php?id=en:docs:fapi:mougetptrshape

Last update: **2021/11/04 13:11**