



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=06H

Version

1 and higher

Brief

DIRECT CONSOLE OUTPUT/INPUT

Family API

[DosWrite](#) [DosRead](#)

Input

```
AH = 06h  
DL = output character (except FFh)  
DL = FFh - input character
```

Return

On output:

```
AL = character output (despite official docs which state nothing is  
returned) (at least DOS 2.1-7.0)
```

On input:

```
ZF set if no character available  
AL = 00h
```

```
ZF clear if character available
```

AL = character read

Notes

does not check ^C/^Break

writes to standard output, which is always the screen under DOS 1.x, but may be redirected under DOS 2+

if the returned character is 00h, the user pressed a key with an extended keycode, which will be returned by the next call of this function

this function reads from standard input, which is always the keyboard under DOS 1.x, but may be redirected under DOS 2+

although the return of AL=00h when no characters are available is not documented, some programs rely on this behavior

See also

AH=02h,AH=09h,AH=0BH

Note

Text based on Ralf Brown Interrupt List Release 61

DOS API	
Process manager	INT 20H, INT 21H: 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, INT 21H: 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, INT 21H: 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, INT 21H: 3300H, 3301H, 3302H
Memory manager	INT 21H: 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	INT 21H: 2AH, 2BH, 2CH, 2DH
Misc	INT 21H: 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	INT 21H: 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H

DOS API	
Devices	INT 21H: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H
Network	INT 21H: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAIInfo @ClS
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushhev · 0 Comments

2018/09/04 17:23 · prokushhev · 0 Comments

Family API	
DOS	Process Manager DosBeep DosExit DosSleep DosExecPgm
	File Manager DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHand State DosNewSize DosBufReset DosQFHand State DosSet FSinfo
	Memory Manager DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreateCS Alias
	NLS DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time DosSetDateTime DosGetDateTime
	Devices DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals DosHoldSignal DosSetSigHandler
	Misc BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools	BIND
Modules	DOSCALS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushhev · 0 Comments

From:
<https://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:06&rev=1714200857>

Last update: **2024/04/27 06:54**