



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=25H

Version

1 and higher

Brief

SET INTERRUPT VECTOR

Family API

Input

```
AH = 25h
AL = interrupt number
DS:DX -> new interrupt handler
```

Return

none

Notes

this function is preferred over direct modification of the interrupt vector table

some DOS extenders place an API on this function, as it is not directly meaningful in protected mode

under DR DOS 5.0-6.0, this function does not use any of the DOS-internal stacks and may thus be called at any time; however, under Novell DOS 7.0 - DR-DOS 7.02, this function was not reentrant. Since 1998/05/29, DR-DOS 7.03 no longer uses any internal stacks and tests for this function much earlier, to allow a minimal stack usage of just two words in addition to the IRET frame, allowing it to be called from INT 21h functions, specifically device drivers. This fixes the MCS SMB client

Novell NetWare (except the new DOS Requester) monitors the offset of any INT 24 set, and if equal to the value at startup, substitutes its own handler to allow handling of network errors; this introduces the potential bug that any program whose INT 24 handler offset happens to be the same as COMMAND.COM's will not have its INT 24 handler installed

See also

AH=[35h](#)

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H , INT 21H : 00H , 25H , 26H , 31H , 34H , 35H , 4BH , 4CH , 4DH , 50H , 51H , 52H , 55H , 62H , INT 22H , INT 27H , INT 28H
File manager	INT 25H , INT 26H , INT 21H : 0DH , 0EH , 0FH , 10H , 11H , 12H , 13H , 14H , 15H , 16H , 17H , 19H , 1AH , 1BH , 1CH , 21H , 22H , 23H , 24H , 27H , 28H , 29H , 2EH , 2FH , 32H , 3305H , 36H , 39H , 3AH , 3BH , 3CH , 3DH , 3EH , 3FH , 40H , 41H , 42H , 4300H , 4301H , 45H , 45H , 46H , 4EH , 4FH , 54H , 56H , 5700H , 5701H , 5AH , 5BH , 5c00H , 5c01H , 60H , 67H , 68H , 6900H , 6901H , 6AH , 6CH
Character Device I/O	INT 29H , INT 21H : 01H , 02H , 03H , 04H , 05H , 06H , 07H , 08H , 09H , 0AH , 0BH , 0AH , 0CH , 5D07H , 5D08H , 5D09H , 5D0AH
Signals	INT 23H , INT 24H , INT 21H : 3300H , 3301H , 3302H
Memory manager	INT 21H : 48H , 49H , 4AH , 5800H , 5801H , 5802H , 5803H
Date and Time	INT 21H : 2AH , 2BH , 2CH , 2DH
Misc	INT 21H : 30H , 3306H , 3700H , 3701H , 3702H , 3703H , 59H
NLS	INT 21H : 3303H , 3304H , 3800H , 3801H , 6300H , 6301H , 6301H , 6500H , 6501H , 6502H , 6503H , 6504H , 6505H , 6506H , 6507H , 6520H , 6521H , 6522H , 6523H , 65A0H , 65A1H , 65A2H , 6601H , 6602H
Devices	INT 21H : 4400H , 4401H , 4402H , 4403H , 4404H , 4405H , 4406H , 4407H , 4408H , 4409H , 440AH , 440BH , 440CH , 440DH , 440EH , 440FH , 4410H , 4411H , 53H
Network	INT 21H : 5E00H , 5E01H , 5E02H , 5E03H , 5E04H , 5E05H , 5F00H , 5F01H , 5F02H , 5F03H , 5F04H , 5F05H , 5F07H , 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @CIs
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat

osFree Macro Library

Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

Family API

DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
KBD	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:

<https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://ftp.osfree.org/doku/doku.php?id=en:docs:dos:api:int21:25&rev=1714620231>Last update: **2024/05/02 03:23**