



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

## DosGetEnv

This call returns the address of the process environment string for the current process.

### Syntax

DosGetEnv (EnvSegment, CmdOffset)

### Parameters

;EnvSegment (PSEL) - output : Address of the selector for the environment segment. ;CmdOffset (PUSHORT) - output : Address of the offset to the command line within the environment segment.

### Return Code

;rc (USHORT) - return:Return code descriptions are: \* 0 NO\_ERROR \* 12 ERROR\_INVALID\_ACCESS

### Remarks

DosGetEnv can be used by dynamic link library routines that need to determine the environment for the current process.

When a process issues [DosExecPgm](#) to start another process, the program that receives control is returned a pointer to the environment segment.

### Bindings

#### C Binding

```
<PRE> #define INCL_DOSMISC
```

```
USHORT rc = DosGetEnv(EnvSegment, CmdOffset);
```

```
PUSHORT EnvSegment; /* Selector (returned) */ PUSHORT CmdOffset; /* Command line offset
(returned) */
```

```
USHORT rc; /* return code */ </PRE>
```

## MASM

```
<PRE> EXTRN DosGetEnv:FAR INCL_DOSMISC EQU 1
```

```
PUSH@ WORD EnvSegment ;Selector (returned) PUSH@ WORD CmdOffset ;Command line offset
(returned) CALL DosGetEnv
```

```
Returns WORD </PRE>
```

## Example Code

The following example shows how one may obtain information for program initialization. The program locates the environment segment and prints the name of the command from the command line. It then obtains the OS/2 version number and prints it. <PRE> #define INCL\_DOS #include <os2.h> #define ENVVARNAME "PATH"

```
main() {
```

```
SEL      EnvSel;          /* Environment segment selector (returned) */
USHORT   CmdOffset;      /* Offset into env. seg. of command line (returned)
*/
PSZ FAR  *Commandline;   /* Pointer made by EnvSel and CmdOffset */
USHORT   Version;        /* Version numbers (returned) */
BYTE     MajorVer;       /* Major version number */
BYTE     MinorVer;       /* Minor version number */
USHORT   rc;             /* return code */
```

```
/** Locate environment segment and offset of command line. **/
if(!(rc=DosGetEnv(&EnvSel,          /* Env. seg. selector (returned) */
                 &CmdOffset))) /* Offset of command line (returned) */
    printf("Environment located; selector is %x offset is %x\n", EnvSel,
           CmdOffset);
```

```
/** Use a macro to make a far pointer out of selector:offset pair. **/
/** Notice the far-string pointer specification (%Fs) used to print **/
```

```
Commandline = MAKEP(EnvSel, CmdOffset);
printf("Command entered is %Fs.\n", Commandline);
```

```
/** Obtain and print version info; use macros to extract info. **/
/** We need to divide by 10 to obtain true version numbers. **/
```

```
if(!(rc=DosGetVersion(&Version)))
```

```
{
  MajorVer = HIBYTE(Version) / 10;
  MinorVer = LOBYTE(Version) / 10;
  printf("This is OS/2 version %d.%d\n", MajorVer, MinorVer);
}
```

} </PRE>

# Note

Text based on <http://www.edm2.com/index.php/DosGetEnv>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDSCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From: <https://ftp.osfree.org/doku/> - osFree wiki

Permanent link: <https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:dosgetenv&rev=1629431107>

Last update: 2021/08/20 03:45



