



# KbdGetStatus

This call gets the current state of the keyboard.

## Syntax

KbdGetStatus (StatData, KbdHandle)

## Parameters

;StatData (PKBDINFO) - output : Address of the keyboard status structure: :length (USHORT) : Length, in bytes, of this data structure, including length. 10 Only valid value. :sysstate (USHORT) : State as follows: 'Bit Description' 15-9 Reserved, set to zero. 8 Shift return is on. 7 Length of the turn-around character (meaningful only if bit 6 is on). 6 Turn-around character is modified. 5 Interim character flags are modified. 4 Shift state is modified. 3 ASCII mode is on. 2 Binary mode is on. 1 Echo off. 0 Echo on. :turnchardef (USHORT) : Definition of the turn-around character. In ASCII and extended-ASCII format, the turn-around character is defined as the carriage return. In ASCII format only, the turn-around character is defined in the low-order byte. :intcharflag (USHORT) : Interim character flags: Bit Description 15-8 NLS shift state. 7 Interim character flag is on. 6 Reserved, set to zero. 5 Application requested immediate conversion. 4-0 Reserved, set to zero. :shiftstate (USHORT) : Shift state as follows: 'Bit Description' 15 SysReq key down 14 CapsLock key down 13 NumLock key down 12 ScrollLock key down 11 Right Alt key down 10 Right Ctrl key down 9 Left Alt key down 8 Left Ctrl key down 7 Insert on 6 CapsLock on 5 NumLock on 4 ScrollLock on 3 Either Alt key down 2 Either Ctrl key down 1 Left Shift key down 0 Right Shift key down. ; KbdHandle (HKBD) - input : Default keyboard or the logical keyboard.

## Return Code

rc (USHORT) - return Return code descriptions are: \* 0 NO\_ERROR \* 376 ERROR\_KBD\_INVALID\_LENGTH \* 439 ERROR\_KBD\_INVALID\_HANDLE \* 445 ERROR\_KBD\_FOCUS\_REQUIRED \* 447 ERROR\_KBD\_KEYBOARD\_BUSY \* 464 ERROR\_KBD\_DETACHED \* 504 ERROR\_KBD\_EXTENDED\_SG

## Remarks

The initial state of the keyboard is established by the system at application load time. Some default states may be modified by the application through KbdSetStatus. KbdGetStatus returns only those keyboard parameters initially set by KbdSetStatus. The returned parameters are: \* Input Mode \* Interim Character Flags \* Shift State \* Echo State \* Turnaround Character KbdGetStatus completes only when the handle has access to the physical keyboard (focus) or the handle is 0 and no other handle has the focus.

## Family API Considerations

Some options operate differently in the DOS mode than in the OS/2 mode. Therefore, the following restrictions apply to KbdGetStatus when coding in the DOS mode: \* Interim character is not supported \* TurnAround character is not supported \* NLS\_SHIFT\_STATE is always NULL. \* KbdHandle is ignored.

### Example Code

### C Binding

```
<PRE> typedef struct _KBDINFO { /* kbst */
```

```
    USHORT cb;                /* length in bytes of this structure */  
    USHORT fsMask;           /* bit mask of functions to be altered */  
    USHORT chTurnAround;     /* define TurnAround character */  
    USHORT fsInterim;        /* interim character flags */  
    USHORT fsState;          /* shift states */
```

```
}KBDINFO;
```

```
#define INCL_KBD
```

```
USHORT rc = KbdGetStatus(Structure, KbdHandle);
```

```
PKBDINFO Structure; /* Data structure */ HKBD KbdHandle; /* Keyboard handle */
```

```
USHORT rc; /* return code */ </PRE>
```

### MASM Binding

```
<PRE> KBDINFO struc
```

```
    kbst_cb          dw  ? ;length in bytes of this structure  
    kbst_fsMask      dw  ? ;bit mask of functions to be altered  
    kbst_chTurnAround dw  ? ;define TurnAround character  
    kbst_fsInterim   dw  ? ;interim character flags  
    kbst_fsState     dw  ? ;shift states
```

```
KBDINFO ends
```

```
EXTRN KbdGetStatus:FAR INCL_KBD EQU 1
```

```
PUSH@ OTHER Structure ;Data structure PUSH WORD KbdHandle ;Keyboard handle CALL  
KbdGetStatus
```

```
Returns WORD </PRE>
```

# Note

This text based on [http://www.edm2.com/index.php/KbdGetStatus\\_\(FAPI\)](http://www.edm2.com/index.php/KbdGetStatus_(FAPI))

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From: <https://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link: <https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:kbdgetstatus&rev=1607165276>

Last update: **2020/12/05 10:47**

