

This call suballocates portions of a segment allocated by DosAllocSeg or DosAllocShrSeg, and initialized by DosSubSet.

Syntax

DosSubAlloc (SegSelector, BlockOffset, Size)

Parameters

;SegSelector (SEL) - input : Data segment selector that allocates the memory. ;BlockOffset (PUSHORT)
- output : Address of the allocated block offset. ;Size (USHORT) - input : Memory block size requested in bytes.

Return Code

rc (USHORT) - return Return code descriptions are: * 0 NO_ERROR * 311 ERROR_DOSSUB_NOMEM * 313 ERROR_DOSSUB_BADSIZE

Remarks

Before a segment allocated by [DosAllocSeg](#) or [DosAllocShrSeg](#) can be suballocated, it must first be initialized for suballocation by a call to [DosSubSet](#).

Allocation size must be a multiple of four bytes. Otherwise, it is rounded up to a multiple of four bytes. The maximum value for the size parameter is the size that was set with DosSubSet minus 8. Note that no paragraph (16-byte) alignment is required; all requests are serviced on a byte alignment basis.

A suballocated block of memory in a suballocated segment is freed by a call to DosSubFree.

Example Code

C Binding

```
<PRE> #define INCL_DOSMEMMGR  
  
USHORT rc = DosSubAlloc(SegSelector, BlockOffset, Size);  
  
SEL SegSelector; /* Segment selector */ PUSHORT BlockOffset; /* Block Offset (returned) */ USHORT  
Size; /* Size of requested block */  
  
USHORT rc; /* return code */ </PRE>
```

MASM Binding

```
<PRE> EXTRN DosSubAlloc:Far Incl_DosMemMgr EQU 1
```

```
PUSH WORD SegSelector ;Segment selector PUSH@ WORD BlockOffset ;Block Offset (returned) PUSH
WORD Size ;Size of requested block CALL DosSubAlloc
```

Returns WORD </PRE>

Note

Text based on <http://www.edm2.com/index.php/DosSubAlloc>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FSInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek	
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:
<https://ftp.osfree.org/doku/> - **osFree wiki**



Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:dossuballoc&rev=1535646862>

Last update: **2018/08/30 16:34**