



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

DosSubAlloc

This call suballocates portions of a segment allocated by DosAllocSeg or DosAllocShrSeg, and initialized by DosSubSet.

Syntax

```
DosSubAlloc ( SegSelector, BlockOffset, Size)
```

Parameters

- SegSelector ([SEL](#)) - input : Data segment selector that allocates the memory.
- BlockOffset ([PUSHORT](#)) - output : Address of the allocated block offset.
- Size ([Memory block size requested in bytes. ===== Return Code ===== rc \(\[\[USHORT\]\)](#) - return

Return code descriptions are:

- 0 NO_ERROR
- 311 ERROR_DOSSUB_NOMEM
- 313 ERROR_DOSSUB_BADSIZE

Remarks

Before a segment allocated by [DosAllocSeg](#) or [DosAllocShrSeg](#) can be suballocated, it must first be initialized for suballocation by a call to [DosSubSet](#).

Allocation size must be a multiple of four bytes. Otherwise, it is rounded up to a multiple of four bytes. The maximum value for the size parameter is the size that was set with DosSubSet minus 8. Note that no paragraph (16-byte) alignment is required; all requests are serviced on a byte alignment basis.

A suballocated block of memory in a suballocated segment is freed by a call to [DosSubFree](#).

Example Code

C Binding

```
#define INCL_DOSMEMMGR

USHORT rc = DosSubAlloc(SegSelector, BlockOffset, Size);

SEL           SegSelector;    /* Segment selector */
PUSHORT       BlockOffset;   /* Block Offset (returned) */
USHORT        Size;         /* Size of requested block */

USHORT        rc;           /* return code */
```

MASM Binding

```
EXTRN DosSubAlloc:FAR
INCL_DOSMEMMGR EQU 1

PUSH WORD SegSelector ;Segment selector
PUSH@ WORD BlockOffset ;Block Offset (returned)
PUSH WORD Size ;Size of requested block
CALL DosSubAlloc
```

Returns WORD

Note

Text based on <http://www.edm2.com/index.php/DosSubAlloc>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreateCS Alias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:dossuballoc&rev=1631868555>

Last update: 2021/09/17 08:49