



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

MouOpen

This call opens the mouse device for the current session.

Syntax

```
MouOpen (DriverName, DeviceHandle)
```

Parameters

- DriverName ([PSZ](#)) - input : DriverName is a far pointer to an ASCII string in application storage containing the name of the pointer draw device driver to be used as the pointer-image drawing routine for this session.
 - The name of the device driver must be included in the CONFIG.SYS file at system start-up time. Applications that use the default pointer draw device driver supplied by the system must push a double-word of 0s in place of an address.
 - DriverName has a different definition when the caller is the Base Video Subsystem (BVS). In this case the selector portion of the far address is zero. The offset portion is non-zero and contains a display configuration number (sequentially numbered where 1 is the first display configuration). The MouOpen call issued by BVS is executed on the VioSetMode path. Using the display configuration number passed on the MouOpen call, the Base Mouse Subsystem can detect a change in display configurations. This form of the MouOpen call is not recommended for applications. Applications should either push the far address of an ASCII pointer draw device driver name or push two words of zeros.
- DeviceHandle ([PHMOU](#)) - output :Address of a 1-word value that represents the mouse handle returned to the application.

Return Code

rc ([USHORT](#)) - return

Return code descriptions are:

- 0 NO_ERROR
- 385 ERROR_MOUSE_NO_DEVICE

- 390 ERROR_MOUSE_INV_MODULE_PT
- 466 ERROR_MOU_DETACHED
- 501 ERROR_MOUSE_NO_CONSOLE
- 505 ERROR_MOU_EXTENDED_SG

Remarks

MouOpen initializes the Mouse functions to a known state. The application may have to issue additional mouse functions to establish the environment it desires. For example, after the MouOpen, the collision area is defined to be the size of the entire display. Therefore, to get the pointer to be displayed, the application must issue a [MouDrawPtr](#) to remove the collision area.

The state of the mouse after the first MouOpen is:

- Row/Col scale factors set to 16/8. (See [MouSetScaleFact](#))
- All events reported. (See [MouSetEventMask](#))
- Empty event queue. (See [MouReadEventQue](#) and [MouGetNumQueEl](#))
- All user settable Device Status bits reset. (Set to zero. See [MouSetDevStatus](#))
- Pointer set to center of screen if valid display mode is set. (See [MouSetPtrPos](#))
- Pointer shape set to the default for the pointer device driver currently registered in the session. (See [MouSetPtrShape](#))
- Collision area equal to full screen. (See [MouDrawPtr](#) and [MouRemovePtr](#))

Bindings

C

```
#define INCL_MOU

USHORT rc = MouOpen(DriverName, DeviceHandle);

PSZ     DriverName;    /* Pointer draw driver name */
PHMOU   DeviceHandle; /* Mouse device handle */

USHORT rc;             /* return code */
```

MASM

```
EXTRN MouOpen:FAR
INCL_MOU EQU 1

PUSH@ ASCIIIZ DriverName ;Pointer draw driver name
PUSH@ WORD    DeviceHandle ;Mouse device handle
CALL    MouOpen
```

Returns **WORD**

Related Functions

MouClose

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGet HugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<http://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:mouopen>

Last update: **2021/11/04 13:12**