



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

VioWrtCellStr

This call writes a string of character-attribute pairs (cells) to the display.

Syntax

```
VioWrtCellStr (CellStr, Length, Row, Column, VioHandle)
```

Parameters

- CellStr (PCH) - input : Address of the string of character-attribute(s) cells to be written.
- Length (USHORT) - input : Length, in bytes, of the string to be written. Each character-attribute(s) cell is 2 or 4 bytes.
- Row (USHORT) - input : Starting cursor row.
- Column (USHORT) - input : Starting cursor column.
- VioHandle (HVIO) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

Return Code

rc (USHORT) - return

Return code descriptions are:

- 0 NO_ERROR
- 355 ERROR_VIO_MODE
- 358 ERROR_VIO_ROW
- 359 ERROR_VIO_COL
- 436 ERROR_VIO_INVALID_HANDLE
- 465 ERROR_VIO_DETACHED

Remarks

If a string write gets to the end of the line and is not complete, the string write continues at the beginning of the next line. If the write gets to the end of the screen, the write terminates.

PM Considerations

Write a character-attribute string to the Advanced VIO presentation space. The caller must specify the starting location on the presentation space where the string is to be written.

Bindings

C Binding

```
#define INCL_VIO

USHORT rc = VioWrtCellStr(CellStr, Length, Row, Column, VioHandle);

PCH          CellStr;      /* String to be written */
USHORT       Length;       /* Length of string */
USHORT       Row;         /* Starting row position for output */
USHORT       Column;      /* Starting column position for output */
HVI0         VioHandle;   /* Video handle */

USHORT       rc;          /* return code */
```

MASM Binding

```
EXTRN VioWrtCellStr:FAR
INCL_VIO EQU 1

PUSH@ OTHER CellStr      ;String to be written
PUSH WORD    Length       ;Length of string
PUSH WORD    Row          ;Starting row position for output
PUSH WORD    Column       ;Starting column position for output
PUSH WORD    VioHandle    ;Video handle
CALL VioWrtCellStr

Returns WORD
```

Note

Text based on [http://www.edm2.com/index.php/VioWrtCellStr_\(FAPI\)](http://www.edm2.com/index.php/VioWrtCellStr_(FAPI))

Family API	
DOS	Process Manager DosBeep DosExit DosSleep DosExecPgm
	File Manager DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time DosSet Date Time DosGet Date Time
	Devices DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals DosHoldSignal DosSet Sig Handler
	Misc BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD	KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek
VIO	VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str VioScroll Up VioScroll Dn VioScroll If VioScroll Rt VioScrUnLock VioSet Cur Pos VioSet Cur Type VioSet Mode VioGet Mode VioShow Buf VioWrt Cell Str VioWrt Char Str VioWrt Char Str Att VioWrt N Attr VioWrt N Cell VioWrt N Char VioWrt TTY VioScr Lock VioPop Up
Tools	BIND
Modules	DOSCALLS.DLL VIOCALS.DLL KBDCALS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:viowrtcellstr>

Last update: **2021/09/19 04:19**