



Please help to find info about enries marked as *No info*

BVSCALLS


This is forwarder DLL to [DOSCALLS.DLL](#)


Ordinal	Name	Desc	Status
1	BVSGETPTRDRAWNAME	Forwarder to DOSCALLS.847	Done
3	BVSMMAIN	Forwarder to DOSCALLS.845	Done
4	BVSREDRAWSIZE	Forwarder to DOSCALLS.846	Done

BVSMMAIN functions number

Number	Name
0	VioGetPhysBuf
1	VioGetBuf
2	VioShowBuf
3	VioGetCurPos
4	VioGetCurType
5	VioGetMode
6	VioSetCurPos
7	VioSetCurType
8	VioSetMode
9	VioReadCharStr
10	VioReadCellStr
11	VioWrtNChar
12	VioWrtNAttr
13	VioWrtNCell
14	VioWrtCharStr
15	VioWrtCharStrAtt
16	VioWrtCellStr
17	VioWrtTTY
18	VioScrollUp
19	VioScrollDn
20	VioScrollLf
21	VioScrollRt
22	VioSetAnsi
23	VioGetAnsi
24	VioPrtSc
25	VioScrLock
26	VioScrUnLock
27	VioSavRedrawWait
28	VioSavRedrawUndo
29	VioPopUp

OS/2 DLLs	
Base API	DOSCALLS EMXWRAP SUB32 ANSICALL NLS MSG MONCALLS KBDSCALLS MOUCALLS VIOCALLS SESMGR BKSCALLS BMSCALLS BVSCALLS NAMPIPES QUECALLS OS2CHAR
Bidirectional NLS	BDCALLS BDCALLS32 BDIME BDBVH BDVIEW BDWPCLS BIDIPM PMBIDI
Unicode API	UCONV UNIKBD LIBUNI
BVH (Base Video Handlers)	BVHINIT BVHMPA BVHVGA BVHSVGA BVHWNDW
GRADD subsystem	VMAN SOFTDRAW GRE2VMAN GENGRADD
IPF (Information Presentation facility)	HELPMGR HPMGRMRI MINXOBJ IBMHMGR NEWVIEW MINXMRI ERRTXT
REXX	REXX REXXAPI REXXUTIL REGINA
The core PM DLL's	PMMERGE PMMRGRES PMSHAPI PMSHLTKT PMGRE PMGPI PMDRAG PMCTLS PMMLE PMSPL PMVIOP PMWIN
Open32	PMWINX MIRRORS REGISTRY
Intelligent Font Interface drivers	PMATM TRUETYPE PMUNIF FREETYPE PMPRE
Data Exchange	PMCLIP PMDDE PMDDEML
VDM PM interface	PMVDMH PMVDMP SEAMLESS SHIELD
WPS	PMWP PMWPMRU PMVDDROP
Miscellaneous	PMPIC PMTKT MVDM





2016/07/25 02:16 · prokushev · 0 Comments

From:
<http://www.osfree.org/doku/> - **osFree wiki**

Permanent link:
<http://www.osfree.org/doku/doku.php?id=en:docs:os2:modules:bvscalls>

Last update: **2021/09/10 02:43**