

This call updates the physical display buffer with the logical video buffer (LVB).

### Syntax

VioShowBuf (Offset, Length, VioHandle)

### Parameters

;Offset (USHORT) - input : Starting offset within the logical video buffer at which the update to the screen is to start. ;Length (USHORT) - input : Length of the area to be updated to the screen. ;VioHandle (HVIO) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

### Return Code

rc (USHORT) - return Return code descriptions are: \* 0 NO\_ERROR \* 355 ERROR\_VIO\_MODE \* 430 ERROR\_VIO\_ILLEGAL\_DURING\_POPUP \* 436 ERROR\_VIO\_INVALID\_HANDLE \* 465 ERROR\_VIO\_DETACHED

### Remarks

VioShowBuf is ignored unless it is issued by a process that has previously called VioGetBuf and that is currently executing in the foreground.

### PM Considerations

This function updates the display with the Advanced VIO presentation space.

### Example Code

### C Binding

```
<PRE> #define INCL_VIO
USHORT rc = VioShowBuf(Offset, Length, VioHandle);
USHORT Offset; /* Offset into LVB */ USHORT Length; /* Length */ HVIO VioHandle; /* Video handle */
USHORT rc; /* return code */ </PRE>
```

### MASM Binding

```
<PRE> EXTRN VioShowBuf:FAR INCL_VIO EQU 1
```

PUSH WORD Offset ;Offset into LVB PUSH WORD Length ;Length PUSH WORD VioHandle ;Video handle  
CALL VioShowBuf

Returns WORD </PRE>

## Note

Text based on [http://www.edm2.com/index.php/VioShowBuf\\_\(FAP\)](http://www.edm2.com/index.php/VioShowBuf_(FAP))

| Family API |                 |                                                                                                                                                                                                                                                                                                                                                                              |
|------------|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DOS        | Process Manager | DosBeep DosExit DosSleep DosExecPgm                                                                                                                                                                                                                                                                                                                                          |
|            | File Manager    | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
|            | Memory Manager  | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias                                                                                                                                                                                                                                           |
|            | NLS             | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage                                                                                                                                                                                                                                                                |
|            | Date and Time   | DosSetDateTime DosGetDateTime                                                                                                                                                                                                                                                                                                                                                |
|            | Devices         | DosDevConfig DosDevIOctl DosDevIOctl2                                                                                                                                                                                                                                                                                                                                        |
|            | Signals         | DosHoldSignal DosSetSigHandler                                                                                                                                                                                                                                                                                                                                               |
|            | Misc            | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec                                                                                                                                                                                                                                                                                          |
| KBD        |                 | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek                                                                                                                                                                                                                                                                                                       |
| VIO        |                 | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp                                        |
| Tools      |                 | BIND                                                                                                                                                                                                                                                                                                                                                                         |
| Modules    |                 | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL                                                                                                                                                                                                                                                                                                                               |
| Libraries  |                 | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB                                                                                                                                                                                                                                                                                                                        |

2018/08/25 15:05 · prokushev · 0 Comments

From:  
<http://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:  
<http://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:vioshowbuf&rev=1535796506>

Last update: **2018/09/01 10:08**

