

Errors Returned from Base OS/2 Calls

- 0 NO_ERROR No error occurred.
- 1 ERROR_INVALID_FUNCTION Invalid function number.
- 2 ERROR_FILE_NOT_FOUND File not found.
- 3 ERROR_PATH_NOT_FOUND Path not found.
- 4 ERROR_TOO_MANY_OPEN_FILES Too many open files (no handles left).
- 5 ERROR_ACCESS_DENIED Access denied.
- 6 ERROR_INVALID_HANDLE Invalid handle.
- 7 ERROR_ARENA_TRASHED Memory control blocks destroyed.
- 8 ERROR_NOT_ENOUGH_MEMORY Insufficient memory.
- 9 ERROR_INVALID_BLOCK Invalid memory-block address.
- 10 ERROR_BAD_ENVIRONMENT Invalid environment.
- 11 ERROR_BAD_FORMAT Invalid format.
- 12 ERROR_INVALID_ACCESS Invalid access code.
- 13 ERROR_INVALID_DATA Invalid data.
- 14 Reserved.
- 15 ERROR_INVALID_DRIVE Invalid drive specified.
- 16 ERROR_CURRENT_DIRECTORY Attempting to remove current directory.
- 17 ERROR_NOT_SAME_DEVICE Not same device.
- 18 ERROR_NO_MORE_FILES No more files.
- 19 ERROR_WRITE_PROTECT Attempt to write on write-protected diskette.
- 20 ERROR_BAD_UNIT Unknown unit.
- 21 ERROR_NOT_READY Drive not ready.
- 22 ERROR_BAD_COMMAND Unknown command.
- 23 ERROR_CRC Data error (CRC).
- 24 ERROR_BAD_LENGTH Bad request structure length.
- 25 ERROR_SEEK Seek error.

- 26 ERROR_NOT_DOS_DISK Unknown media type.
- 27 ERROR_SECTOR_NOT_FOUND Sector not found.
- 28 ERROR_OUT_OF_PAPER Printer out of paper.
- 29 ERROR_WRITE_FAULT Write fault.
- 30 ERROR_READ_FAULT Read fault.
- 31 ERROR_GEN_FAILURE General failure.
- 32 ERROR_SHARING_VIOLATION Sharing violation.
- 33 ERROR_LOCK_VIOLATION Lock violation.
- 34 ERROR_WRONG_DISK Invalid disk change.
- 35 ERROR_FCB_UNAVAILABLE FCB unavailable.
- 36 ERROR_SHARING_BUFFER_EXCEEDED Sharing buffer overflow.
- 37-49 Reserved.
- 50 ERROR_NOT_SUPPORTED Network request not supported.
- 65 Access denied.
- 73-79 Reserved.
- 80 ERROR_FILE_EXISTS File exists.
- 81 ERROR_DUP_FCB Reserved.
- 82 ERROR_CANNOT_MAKE Cannot make directory entry.
- 83 ERROR_FAIL_I24 Fail on INT 24.
- 84 ERROR_OUT_OF_STRUCTURES Too many redirections.
- 85 ERROR_ALREADY_ASSIGNED Duplicate redirection.
- 86 ERROR_INVALID_PASSWORD Invalid password.
- 87 ERROR_INVALID_PARAMETER Invalid parameter.
- 88 ERROR_NET_WRITE_FAULT Network device fault.
- 89 ERROR_NO_PROC_SLOTS No process slots available.
- 90 ERROR_NOT_FROZEN System error.
- 91 ERR_TSTOVFL Timer service table overflow.
- 92 ERR_TSTDUP Timer service table duplicate.

- 93 ERROR_NO_ITEMS No items to work on.
- 95 ERROR_INTERRUPT Interrupted system call.
- 99 ERROR_DEVICE_IN_USE Device in use.
- 100 ERROR_TOO_MANY_SEMAPHORES User/system open semaphore limit exceeded.
- 101 ERROR_EXCL_SEM_ALREADY_OWNED Exclusive semaphore already owned.
- 102 ERROR_SEM_IS_SET DosCloseSem found semaphore set.
- 103 ERROR_TOO_MANY_SEM_REQUESTS Too many exclusive semaphore requests.
- 104 ERROR_INVALID_AT_INTERRUPT_TIME Operation invalid at interrupt time.
- 105 ERROR_SEM_OWNER_DIED Previous semaphore owner terminated without freeing semaphore.
- 106 ERROR_SEM_USER_LIMIT Semaphore limit exceeded.
- 107 ERROR_DISK_CHANGE Insert drive B disk into drive A.
- 108 ERROR_DRIVE_LOCKED Drive locked by another process.
- 109 ERROR_BROKEN_PIPE Write on pipe with no reader.
- 110 ERROR_OPEN_FAILED Open/create failed due to explicit fail command.
- 111 ERROR_BUFFER_OVERFLOW Buffer passed to system call too small to hold return data.
- 112 ERROR_DISK_FULL Not enough space on the disk.
- 113 ERROR_NO_MORE_SEARCH_HANDLES Cannot allocate another search structure and handle.
- 114 ERROR_INVALID_TARGET_HANDLE Target handle in DosDupHandle invalid.
- 115 ERROR_PROTECTION_VIOLATION Bad user virtual address.
- 116 ERROR_VIOKBD_REQUEST Error on display write or keyboard read.
- 117 ERROR_INVALID_CATEGORY Category for DevIOctl not defined.
- 118 ERROR_INVALID_VERIFY_SWITCH Invalid value passed for verify flag.
- 119 ERROR_BAD_DRIVER_LEVEL Level four driver not found.
- 120 ERROR_CALL_NOT_IMPLEMENTED Invalid function called.
- 121 ERROR_SEM_TIMEOUT Time out occurred from semaphore API function.
- 122 ERROR_INSUFFICIENT_BUFFER Data buffer too small.
- 123 ERROR_INVALID_NAME Illegal character or bad file-system name.
- 124 ERROR_INVALID_LEVEL Non-implemented level for information retrieval or setting.

- 125 ERROR_NO_VOLUME_LABEL No volume label found with DosQFInfo command.
- 126 ERROR_MOD_NOT_FOUND Module handle not found with getprocaddr, getmodhandle.
- 127 ERROR_PROC_NOT_FOUND Procedure address not found with getprocaddr.
- 128 ERROR_WAIT_NO_CHILDREN DosCwait finds no children.
- 129 ERROR_CHILD_NOT_COMPLETE DosCwait children not terminated.
- 130 ERROR_DIRECT_ACCESS_HANDLE Handle operation invalid for direct disk-accesshandles.
- 131 ERROR_NEGATIVE_SEEK Attempting seek to negative offset.
- 132 ERROR_SEEK_ON_DEVICE Application trying to seek on device or pipe.
- 133 ERROR_IS_JOIN_TARGET Drive has previously joined drives.
- 134 ERROR_IS_JOINED Drive is already joined.
- 135 ERROR_IS_SUBSTED Drive is already substituted.
- 136 ERROR_NOT_JOINED Cannot delete drive that is not joined.
- 137 ERROR_NOT_SUBSTED Cannot delete drive that is not substituted.
- 138 ERROR_JOIN_TO_JOIN Cannot join to a joined drive.
- 139 ERROR_SUBST_TO_SUBST Cannot substitute to a substituted drive.
- 140 ERROR_JOIN_TO_SUBST Cannot join to a substituted drive.
- 141 ERROR_SUBST_TO_JOIN Cannot substitute to a joined drive.
- 142 ERROR_BUSY_DRIVE Specified drive is busy.
- 143 ERROR_SAME_DRIVE Cannot join or substitute a drive to a directory on the same drive.
- 144 ERROR_DIR_NOT_ROOT Directory must be a subdirectory of the root.
- 145 ERROR_DIR_NOT_EMPTY Directory must be empty to use join command.
- 146 ERROR_IS_SUBST_PATH Path specified is being used in a substitute.
- 147 ERROR_IS_JOIN_PATH Path specified is being used in join.
- 148 ERROR_PATH_BUSY Path specified is being used by another process.
- 149 ERROR_IS_SUBST_TARGET Cannot join or substitute drive having directory that is target of a previous substitute.
- 150 ERROR_SYSTEM_TRACE System trace error.
- 151 ERROR_INVALID_EVENT_COUNT DosMuxSemWait errors.

- 152 ERROR_TOO_MANY_MUXWAITERS System limit of 100 entries reached.
- 153 ERROR_INVALID_LIST_FORMAT Invalid list format.
- 154 ERROR_LABEL_TOO_LONG Volume label too big.
- 155 ERROR_TOO_MANY_TCBS Cannot create another TCB.
- 156 ERROR_SIGNAL_REFUSED Signal refused.
- 157 ERROR_DISCARDED Segment is discarded.
- 158 ERROR_NOT_LOCKED Segment not locked.
- 159 ERROR_BAD_THREADID_ADDR Bad thread-identity address.
- 160 ERROR_BAD_ARGUMENTS Bad environment pointer.
- 161 ERROR_BAD_PATHNAME Bad path name passed to exec.
- 162 ERROR_SIGNAL_PENDING Signal already pending.
- 163 ERROR_UNCERTAIN_MEDIA ERROR_I24 mapping.
- 164 ERROR_MAX_THRDS_REACHED No more process slots.
- 165 ERROR_MONITORS_NOT_SUPPORTED ERROR_I24 mapping.
- 166 ERROR_UNC_DRIVER_NOT_INSTALLED Default redir return code
- 167 ERROR_LOCK_FAILED Locking failed.
- 168 ERROR_SWAPIO_FAILED Swap IO failed.
- 169 ERROR_SWAPIN_FAILED Swap in failed.
- 170 ERROR_BUSY Busy.
- 180 ERROR_INVALID_SEGMENT_NUMBER Invalid segment number.
- 181 ERROR_INVALID_CALLGATE Invalid call gate.
- 182 ERROR_INVALID_ORDINAL Invalid ordinal.
- 183 ERROR_ALREADY_EXISTS Shared segment already exists.
- 184 ERROR_NO_CHILD_PROCESS No child process to wait for.
- 185 ERROR_CHILD_ALIVE_NOWAIT NoWait specified and child alive.
- 186 ERROR_INVALID_FLAG_NUMBER Invalid flag number.
- 187 ERROR_SEM_NOT_FOUND Semaphore does not exist.
- 188 ERROR_INVALID_STARTING_CODESEG Invalid starting code segment,incorrect END (label)

directive.

189 ERROR_INVALID_STACKSEG Invalid stack segment.

190 ERROR_INVALID_MODULETYPE Invalid module type - dynamic-link library file cannot be used as an application. Application cannot be used as a dynamic-link library.

191 ERROR_INVALID_EXE_SIGNATURE Invalid EXE signature - file is DOS mode program or improper program.

192 ERROR_EXE_MARKED_INVALID EXE marked invalid - link detected errors when application created.

193 ERROR_BAD_EXE_FORMAT Bad EXE format - file is DOS mode program or improper program.

194 ERROR_ITERATED_DATA_EXCEEDS_64K Iterated data exceeds 64KB - more than 64KB of data in one of the segments of the file.

195 ERROR_INVALID_MINALLOCSIZE Invalid minimum allocation size - size is specified to be less than the size of the segment data in the file.

196 ERROR_DYNLINK_FROM_INVALID_RING Dynamic link from invalid privilege level - privilege level 2 routine cannot link to dynamic-link libraries.

197 ERROR_IOPL_NOT_ENABLED IOPL not enabled - IOPL set to "NO" in CONFIG.SYS.

198 ERROR_INVALID_SEGDPL Invalid segment descriptor privilege level - can only have privilege levels of 2 and 3.

199 ERROR_AUTODATASEG_EXCEEDS_64k Automatic data segment exceeds 64KB.

200 ERROR_RING2SEG_MUST_BE_MOVABLE Privilege level 2 segment must be movable.

201 ERROR_RELOC_CHAIN_XEEDS_SEGLIM Relocation chain exceeds segment limit.

202 ERROR_INFLOOP_IN_RELOC_CHAIN Infinite loop in relocation chain segment.

203 ERROR_ENVVAR_NOT_FOUND Environment variable not found.

204 ERROR_NOT_CURRENT_CTRY Not current country.

205 ERROR_NO_SIGNAL_SENT No signal sent - no process in the command subtree has a signal handler.

206 ERROR_FILENAME_EXCED_RANGE File name or extension greater than "8.3" characters.

207 ERROR_RING2_STACK_IN_USE Privilege level 2 stack in use.

208 ERROR_META_EXPANSION_TOO_LONG Meta (global) expansion is too long.

209 ERROR_INVALID_SIGNAL_NUMBER Invalid signal number.

210 ERROR_THREAD_1_INACTIVE Inactive thread.

211 ERROR_INFO_NOT_AVAIL File system information not available for this file.

- 212 ERROR_LOCKED Locked error.
- 213 ERROR_BAD_DYNALINK Attempted to execute non-family API in DOS mode.
- 214 ERROR_TOO_MANY_MODULES Too many modules.
- 215 ERROR_NESTING_NOT_ALLOWED Nesting not allowed.
- 217 ERROR_ZOMBIE_PROCESS Zombie process.
- 218 ERROR_STACK_IN_HIGH_MEMORY Stack in high memory.
- 219 ERROR_INVALID_EXITROUTINE_RING Invalid exit routine ring.
- 220 ERROR_GETBUF_FAILED Get buffer failed.
- 221 ERROR_FLUSHBUF_FAILED Flush buffer failed.
- 222 ERROR_TRANSFER_TOO_LONG Transfer is too long.
- 228 ERROR_NO_CHILDREN No child process.
- 229 ERROR_INVALID_SCREEN_GROUP Invalid session.
- 230 ERROR_BAD_PIPE Non-existent pipe or bad operation.
- 231 ERROR_PIPE_BUSY Pipe is busy.
- 232 ERROR_NO_DATA No data available on non-blocking read.
- 233 ERROR_PIPE_NOT_CONNECTED Pipe was disconnected by server.
- 234 ERROR_MORE_DATA More data is available.
- 240 ERROR_VC_DISCONNECTED Session was dropped due to errors.
- 250 ERROR_CIRCULARITY_REQUESTED Renaming a directory that would cause a circularity problem.
- 251 ERROR_DIRECTORY_IN_CDS Renaming a directory that is in use.
- 252 ERROR_INVALID_FSD_NAME Trying to access nonexistent FSD.
- 253 ERROR_INVALID_PATH Bad pseudo device.
- 254 ERROR_INVALID_EA_NAME Bad character in name, or bad cbName.
- 255 ERROR_EA_LIST_INCONSISTENT List does not match its size, or bad EAs in list.
- 256 ERROR_EA_LIST_TOO_LONG FEAList > 64K-1 bytes.
- 257 ERROR_NO_META_MATCH String doesn't match expression.
- 259 ERROR_NO_MORE_ITEMS DosQFSAttach ordinal query.
- 260 ERROR_SEARCH_STRUC_REUSED DOS mode findfirst/next search structure reused.

- 261 ERROR_CHAR_NOT_FOUND Character not found.
- 262 ERROR_TOO_MUCH_STACK Stack request exceeds system limit.
- 263 ERROR_INVALID_ATTR Invalid attribute.
- 264 ERROR_INVALID_STARTING_RING Invalid starting ring.
- 265 ERROR_INVALID_DLL_INIT_RING Invalid DLL INIT ring.
- 266 ERROR_CANNOT_COPY Cannot copy.
- 267 ERROR_DIRECTORY Used by DOSCOPY in doscall1.
- 268 ERROR_OPLOCKED_FILE Oplocked file.
- 269 ERROR_OPLOCK_THREAD_EXISTS Oplock thread exists.
- 270 ERROR_VOLUME_CHANGED Volume changed.
- 271-273 Reserved.
- 274 ERROR_ALREADY_SHUTDOWN System already shutdown.
- 275 ERROR_EAS_DIDNT_FIT EAS didnt fit.
- 303 ERROR_INVALID_PROCID Invalid process identity.
- 304 ERROR_INVALID_PDELTA Invalid priority delta.
- 305 ERROR_NOT_DESCENDANT Not descendant.
- 306 ERROR_NOT_SESSION_MANAGER Requestor not session manager.
- 307 ERROR_INVALID_PCLASS Invalid P class.
- 308 ERROR_INVALID_SCOPE Invalid scope.
- 309 ERROR_INVALID_THREADID Invalid thread identity.
- 310 ERROR_DOSSUB_SHRINK Cannot shrink segment - DosSubSet.
- 311 ERROR_DOSSUB_NOMEM No memory to satisfy request - DosSubAlloc .
- 312 ERROR_DOSSUB_OVERLAP Overlap of specified block with an allocated memory - DosSubFree.
- 313 ERROR_DOSSUB_BADSIZE Bad size parameter - DosSubAlloc or DosSubFree.
- 314 ERROR_DOSSUB_BADFLAG Bad flag parameter - DosSubSet.
- 315 ERROR_DOSSUB_BADSELECTOR Invalid segment selector.
- 316 ERROR_MR_MSG_TOO_LONG Message too long for buffer.
- 317 ERROR_MR_MID_NOT_FOUND Message identity number not found.

- 318 ERROR_MR_UN_ACC_MSGF Unable to access message file.
- 319 ERROR_MR_INV_MSGF_FORMAT Invalid message file format.
- 320 ERROR_MR_INV_IVCOUNT Invalid insertion variable count.
- 321 ERROR_MR_UN_PERFORM Unable to perform function.
- 322 ERROR_TS_WAKEUP Unable to wake up.
- 323 ERROR_TS_SEMHANDLE Invalid system semaphore.
- 324 ERROR_TS_NOTIMER No timers available.
- 326 ERROR_TS_HANDLE Invalid timer handle.
- 327 ERROR_TS_DATETIME Date or time invalid.
- 328 ERROR_SYS_INTERNAL Internal system error.
- 329 ERROR_QUE_CURRENT_NAME Current queue name does not exist.
- 330 ERROR_QUE_PROC_NOT_OWNED Current process does not own queue.
- 331 ERROR_QUE_PROC_OWNED Current process owns queue.
- 332 ERROR_QUE_DUPLICATE Duplicate queue name.
- 333 ERROR_QUE_ELEMENT_NOT_EXIST Queue element does not exist.
- 334 ERROR_QUE_NO_MEMORY Inadequate queue memory.
- 335 ERROR_QUE_INVALID_NAME Invalid queue name.
- 336 ERROR_QUE_INVALID_PRIORITY Invalid queue priority parameter.
- 337 ERROR_QUE_INVALID_HANDLE Invalid queue handle.
- 338 ERROR_QUE_LINK_NOT_FOUND Queue link not found.
- 339 ERROR_QUE_MEMORY_ERROR Queue memory error.
- 340 ERROR_QUE_PREV_AT_END Previous queue element was at end of queue.
- 341 ERROR_QUE_PROC_NO_ACCESS Process does not have access to queues.
- 342 ERROR_QUE_EMPTY Queue is empty.
- 343 ERROR_QUE_NAME_NOT_EXIST Queue name does not exist.
- 344 ERROR_QUE_NOT_INITIALIZED Queues not initialized.
- 345 ERROR_QUE_UNABLE_TO_ACCESS Unable to access queues.
- 346 ERROR_QUE_UNABLE_TO_ADD Unable to add new queue.

- 347 ERROR_QUE_UNABLE_TO_INIT Unable to initialize queues.
- 349 ERROR_VIO_INVALID_MASK Invalid function replaced.
- 350 ERROR_VIO_PTR Invalid pointer to parameter.
- 351 ERROR_VIO_APTR Invalid pointer to attribute.
- 352 ERROR_VIO_RPTR Invalid pointer to row.
- 353 ERROR_VIO_CPTR Invalid pointer to column.
- 354 ERROR_VIO_LPTR Invalid pointer to length.
- 355 ERROR_VIO_MODE Unsupported screen mode.
- 356 ERROR_VIO_WIDTH Invalid cursor width value.
- 357 ERROR_VIO_ATTR Invalid cursor attribute value.
- 358 ERROR_VIO_ROW Invalid row value.
- 359 ERROR_VIO_COL Invalid column value.
- 360 ERROR_VIO_TOPROW Invalid TopRow value.
- 361 ERROR_VIO_BOTROW Invalid BotRow value.
- 362 ERROR_VIO_RIGHTCOL Invalid right column value.
- 363 ERROR_VIO_LEFTCOL Invalid left column value.
- 364 ERROR_SCS_CALL Call issued by other than sm
- 365 ERROR_SCS_VALUE Value is not for save or restore.
- 366 ERROR_VIO_WAIT_FLAG Invalid wait flag setting.
- 367 ERROR_VIO_UNLOCK Screen not previously locked.
- 368 ERROR_SGS_NOT_SESSION_MGR Caller not session manager.
- 369 ERROR_SMG_INVALID_SGID Invalid session identity.
- 369 ERROR_SMG_INVALID_SESSION_ID Invalid session ID.
- 370 ERROR_SMG_NOSG No sessions available.
- 370 ERROR_SMG_NO_SESSIONS No sessions available.
- 371 ERROR_SMG_GRP_NOT_FOUND Session not found.
- 371 ERROR_SMG_SESSION_NOT_FOUND Session not found.
- 372 ERROR_SMG_SET_TITLE Title sent by shell or parent cannot be changed.

- 373 ERROR_KBD_PARAMETER Invalid parameter to keyboard.
- 374 ERROR_KBD_NO_DEVICE No device.
- 375 ERROR_KBD_INVALID_IOWAIT Invalid I/O wait specified.
- 376 ERROR_KBD_INVALID_LENGTH Invalid length for keyboard.
- 377 ERROR_KBD_INVALID_ECHO_MASK Invalid echo mode mask.
- 378 ERROR_KBD_INVALID_INPUT_MASK Invalid input mode mask.
- 379 ERROR_MON_INVALID_PARMS Invalid parameters to DosMon.
- 380 ERROR_MON_INVALID_DEVNAME Invalid device name string.
- 381 ERROR_MON_INVALID_HANDLE Invalid device handle.
- 382 ERROR_MON_BUFFER_TOO_SMALL Buffer too small.
- 383 ERROR_MON_BUFFER_EMPTY Buffer is empty.
- 384 ERROR_MON_DATA_TOO_LARGE Data record too large.
- 385 ERROR_MOUSE_NO_DEVICE Mouse device closed (invalid device handle).
- 386 ERROR_MOUSE_INV_HANDLE Mouse device closed (invalid device handle).
- 387 ERROR_MOUSE_INV_PARMS Parameters invalid for display mode.
- 388 ERROR_MOUSE_CANT_RESET Function assigned and cannot be reset.
- 389 ERROR_MOUSE_DISPLAY_PARMS Parameters invalid for display mode.
- 390 ERROR_MOUSE_INV_MODULE Module not valid.
- 391 ERROR_MOUSE_INV_ENTRY_PT Entry point not valid.
- 392 ERROR_MOUSE_INV_MASK Function mask invalid.
- 393 NO_ERROR_MOUSE_NO_DATA No valid data.
- 394 NO_ERROR_MOUSE_PTR_DRAWN Pointer drawn.
- 395 ERROR_INVALID_FREQUENCY Invalid frequency for beep.
- 396 ERROR-NLS_NO_COUNTRY_FILE Cannot find COUNTRY.SYS file.
- 397 ERROR-NLS_OPEN_FAILED Cannot open COUNTRY.SYS file.
- 398 ERROR-NLS_NO_CTRY_CODE Country code not found.
- 398 ERROR_NO_COUNTRY_OR_CODEPAGE Country code not found.
- 399 ERROR-NLS_TABLE_TRUNCATED Table returned information truncated, buffer too small.

- 400 ERROR_NLS_BAD_TYPE Selected type does not exist.
- 401 ERROR_NLS_TYPE_NOT_FOUND Selected type not in file.
- 402 ERROR_VIO_SMG_ONLY Valid from session manager only.
- 403 ERROR_VIO_INVALID_ASCIIIZ Invalid ASCIIIZ length.
- 404 ERROR_VIO_DEREGISTER VioDeRegister not allowed.
- 405 ERROR_VIO_NO_POPUP Pop-up window not allocated.
- 406 ERROR_VIO_EXISTING_POPUP Pop-up window on screen (NoWait).
- 407 ERROR_KBD_SMG_ONLY Valid from session manager only.
- 408 ERROR_KBD_INVALID_ASCIIIZ Invalid ASCIIIZ length.
- 409 ERROR_KBD_INVALID_MASK Invalid replacement mask.
- 410 ERROR_KBD_REGISTER KbdRegister not allowed.
- 411 ERROR_KBD_DEREGISTER KbdDeRegister not allowed.
- 412 ERROR_MOUSE_SMG_ONLY Valid from session manager only.
- 413 ERROR_MOUSE_INVALID_ASCIIIZ Invalid ASCIIIZ length.
- 414 ERROR_MOUSE_INVALID_MASK Invalid replacement mask.
- 415 ERROR_MOUSE_REGISTER Mouse register not allowed.
- 416 ERROR_MOUSE_DEREGISTER Mouse deregister not allowed.
- 417 ERROR_SMG_BAD_ACTION Invalid action specified.
- 418 ERROR_SMG_INVALID_CALL_INIT called more than once or invalid session identity.
- 419 ERROR_SCS_SG_NOTFOUND New session number.
- 420 ERROR_SCS_NOT_SHELL Caller is not shell.
- 421 ERROR_VIO_INVALID_PARMS Invalid parameters passed.
- 422 ERROR_VIO_FUNCTION_OWNED Save/restore already owned.
- 423 ERROR_VIO_RETURN Non-destruct return (undo).
- 424 ERROR_SCS_INVALID_FUNCTION Caller invalid function.
- 425 ERROR_SCS_NOT_SESSION_MGR Caller not session manager.
- 426 ERROR_VIO_REGISTER Vio register not allowed.
- 427 ERROR_VIO_NO_MODE_THREAD No mode restore thread in SG.

- 428 ERROR_VIO_NO_SAVE_RESTORE_THD No save/rest thread in SG.
- 429 ERROR_VIO_IN_BG Function invalid in background.
- 430 ERROR_VIO_ILLEGAL_DURING_POPUP Function not allowed during pop-up window.
- 431 ERROR_SMG_NOT_BASESHELL Caller is not the base shell.
- 432 ERROR_SMG_BAD_STATUSREQ Invalid status requested.
- 433 ERROR_QUE_INVALID_WAIT NoWait parameter out of bounds.
- 434 ERROR_VIO_LOCK Error returned from Scroll Lock.
- 435 ERROR_MOUSE_INVALID_IOWAIT Invalid parameters for IOWait.
- 436 ERROR_VIO_INVALID_HANDLE Invalid VIO handle.
- 437 ERROR_VIO_ILLEGAL_DURING_LOCK Function not allowed during screen lock.
- 438 ERROR_VIO_INVALID_LENGTH Invalid VIO length.
- 439 ERROR_KBD_INVALID_HANDLE Invalid KBD handle.
- 440 ERROR_KBD_NO_MORE_HANDLE Ran out of handles.
- 441 ERROR_KBD_CANNOT_CREATE_KCB Unable to create kcb.
- 442 ERROR_KBD_CODEPAGE_LOAD_INCOMPL Unsuccessful code-page load.
- 443 ERROR_KBD_INVALID_CODEPAGE_ID Invalid code-page identity.
- 444 ERROR_KBD_NO_CODEPAGE_SUPPORT No code page support.
- 445 ERROR_KBD_FOCUS_REQUIRED Keyboard focus required.
- 446 ERROR_KBD_FOCUS_ALREADY_ACTIVE Calling thread has an outstanding focus.
- 447 ERROR_KBD_KEYBOARD_BUSY Keyboard busy.
- 448 ERROR_KBD_INVALID_CODEPAGE Invalid code page.
- 449 ERROR_KBD_UNABLE_TO_FOCUS Focus attempt failed.
- 450 ERROR_SMG_SESSION_NON_SELECT Session is not selectable.
- 451 ERROR_SMG_SESSION_NOT_FOREGRND Parent/child session not foreground.
- 452 ERROR_SMG_SESSION_NOT_PARENT Not parent of requested child.
- 453 ERROR_SMG_INVALID_START_MODE Invalid session start mode.
- 454 ERROR_SMG_INVALID_RELATED_OPT Invalid session start related option.
- 455 ERROR_SMG_INVALID_BOND_OPTION Invalid session bond option.

- 456 ERROR_SMG_INVALID_SELECT_OPT Invalid session select option.
- 457 ERROR_SMG_START_IN_BACKGROUND Session started in background.
- 458 ERROR_SMG_INVALID_STOP_OPTION Invalid session stop option.
- 459 ERROR_SMG_BAD_RESERVE Reserved parameters not zero.
- 460 ERROR_SMG_PROCESS_NOT_PARENT Session parent process already exists.
- 461 ERROR_SMG_INVALID_DATA_LENGTH Invalid data length.
- 462 ERROR_SMG_NOT_BOUND Parent not bound.
- 463 ERROR_SMG_RETRY_SUB_ALLOC Retry request block allocation.
- 464 ERROR_KBD_DETACHED This call not allowed for detached PID.
- 465 ERROR_VIO_DETACHED This call disallowed for detached pid.
- 466 ERROR_MOU_DETACHED This call disallowed for detached pid.
- 467 ERROR_VIO_FONT No font available to support mode.
- 468 ERROR_VIO_USER_FONT User font active.
- 469 ERROR_VIO_BAD_CP Invalid code page specified.
- 470 ERROR_VIO_NO_CP System displays do not support code page.
- 471 ERROR_VIO_NA_CP Current display does not support code page.
- 472 ERROR_INVALID_CODE_PAGE Invalid code page.
- 473 ERROR_CPLIST_TOO_SMALL Code page list is too small.
- 474 ERROR_CP_NOT_MOVED Code page not moved.
- 475 ERROR_MODE_SWITCH_INIT Mode switch initialization error.
- 476 ERROR_CODE_PAGE_NOT_FOUND Code page not found.
- 477 ERROR_UNEXPECTED_SLOT_RETURNED Internal error.
- 478 ERROR_SMG_INVALID_TRACE_OPTION Invalid start session trace indicator.
- 479 ERROR_VIO_INTERNAL_RESOURCE VIO internal resource error.
- 480 ERROR_VIO_SHELL_INIT VIO shell initialization error.
- 481 ERROR_SMG_NO_HARD_ERRORS No session manager hard errors.
- 482 ERROR_CP_SWITCH_INCOMPLETE DosSetCp unable to set KBD or VIO code page.
- 483 ERROR_VIO_TRANSPARENT_POPUP Error during VIO pop-up window.

484 ERROR_CRITSEC_OVERFLOW Critical section overflow.

485 ERROR_CRITSEC_UNDERFLOW Critical section underflow.

486 ERROR_VIO_BAD_RESERVE Reserved parameter is not zero.

487 ERROR_INVALID_ADDRESS Bad physical address.

488 ERROR_ZERO_SELECTORS_REQUESTED At least one selector must be requested.

489 ERROR_NOT_ENOUGH_SELECTORS_AVA Not enough GDT selectors to satisfy request.

490 ERROR_INVALID_SELECTOR Not a GDT selector.

491 ERROR_SMG_INVALID_PROGRAM_TYPE Invalid program type.

492 ERROR_SMG_INVALID_PGM_CONTROL Invalid program control.

493 ERROR_SMG_INVALID_INHERIT_OPT Bad inherit option.

494 ERROR_VIO_EXTENDED_SG

495 ERROR_VIO_NOT_PRES_MGR_SG

496 ERROR_VIO_SHIELD_OWNED

497 ERROR_VIO_NO_MORE_HANDLES

498 ERROR_VIO_SEE_ERROR_LOG

499 ERROR_VIO_ASSOCIATED_DC

500 ERROR_KBD_NO_CONSOLE

501 ERROR_MOUSE_NO_CONSOLE

502 ERROR_MOUSE_INVALID_HANDLE

503 ERROR_SMG_INVALID_DEBUG_PARMS

504 ERROR_KBD_EXTENDED_SG

505 ERROR_MOU_EXTENDED_SG

506 ERROR_SMG_INVALID_ICON_FILE

From:
<http://ftp.osfree.org/doku/> - **osFree wiki**

Permanent link:
<http://ftp.osfree.org/doku/doku.php?id=en:ibm:prcp:cpapi&rev=1399995266>

Last update: **2014/05/13 15:34**



