

This call removes a subdirectory from the specified disk.

Syntax

DosRmDir (DirName, Reserved)

Parameters

;DirName (PSZ) - input : Address of the fully qualified path name of the subdirectory being removed.
;Reserved (ULONG) - input : Reserved must be set to zero.

Return Code

rc (USHORT) - return Return code descriptions are:
* 0 NO_ERROR * 2 ERROR_FILE_NOT_FOUND * 3
ERROR_PATH_NOT_FOUND * 5 ERROR_ACCESS_DENIED * 16 ERROR_CURRENT_DIRECTORY * 26
ERROR_NOT_DOS_DISK * 87 ERROR_INVALID_PARAMETER * 108 ERROR_DRIVE_LOCKED * 206
ERROR_FILENAME_EXCED_RANGE

Remarks

The subdirectory must be empty, which means it cannot contain hidden files or directory entries other than the “.” and “..” entries. Files can be deleted with [DosDelete](#).

The root directory and current directory cannot be removed.

Example Code

C Binding

```
<PRE> #define INCL_DOSFILEMGR  
  
USHORT rc = DosRmDir(DirName, Reserved);  
  
PSZ DirName; /* Directory name string */ ULONG 0; /* Reserved (must be zero) */  
  
USHORT rc; /* return code */ </PRE>
```

MASM Binding

```
<PRE> EXTRN DosRmDir:FAR INCL_DOSFILEMGR EQU 1  
  
PUSH@ ASCIIZ DirName ;Directory name string PUSH DWORD 0 ;Reserved (must be zero) CALL  
DosRmDir
```

Returns WORD </PRE>

Note

Text based on <http://www.edm2.com/index.php/DosRmDir>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FSInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGet Huge Shift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:dosrmdir&rev=1535546534>

Last update: **2018/08/29 12:42**