

This call returns the coordinates of the cursor.

## Syntax

VioGetCurPos (Row, Column, VioHandle)

## Parameters

;Row (PUSHORT) - output : Address of the current Row position of the cursor where 0 is the top row.  
;Column (PUSHORT) - output : Address of the current column position of the cursor where 0 is the leftmost column. ;VioHandle (HVIO) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

## Return Code

rc (USHORT) - return Return code descriptions are: \* 0 NO\_ERROR \* 355 ERROR\_VIO\_MODE \* 436  
ERROR\_VIO\_INVALID\_HANDLE \* 465 ERROR\_VIO\_DETACHED

## Remarks

## Example Code

### C Binding

```
<PRE> #define INCL_VIO  
  
USHORT rc = VioGetCurPos(Row, Column, VioHandle);  
  
PUSHORT Row; /* Row return data */ PUSHORT Column; /* Column return data */ HVIO VioHandle; /*  
Vio handle */  
  
USHORT rc; /* return code */ </PRE>
```

### MASM Binding

```
<PRE> EXTRN VioGetCurPos:FAR INCL_VIO EQU 1  
  
PUSH@ WORD Row ;Row return data PUSH@ WORD Column ;Column return data PUSH WORD  
VioHandle ;Vio handle CALL VioGetCurPos  
  
Returns WORD </PRE>
```

# Note

Text based on [http://www.edm2.com/index.php/VioGetCurPos\\_\(FAPI\)](http://www.edm2.com/index.php/VioGetCurPos_(FAPI))

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSet FInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAlloc Huge DosAlloc Seg DosRealloc Huge DosRealloc Seg DosGet Huge Shift DosCreate CS Alias
	NLS	DosCaseMap DosGet Ctry Info DosGet DBCSEv DosSet Ctry Code DosGet Collate DosGet Message DosIns Message DosPut Message
	Date and Time	DosSet Date Time DosGet Date Time
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSet Sig Handler
	Misc	BadDynLink DosGet Env DosGet Machine Mode DosGet Version DosError DosErr Class DosSet Vec
KBD	KbdCharIn KbdFlushBuffer KbdGet Status KbdSet Status KbdStringIn KbdPeek	
VIO	VioGet Buf VioGet Config VioGet Cur Pos VioGet Cur Type VioGet Phys Buf VioRead Cell Str VioRead Char Str Vio Scroll Up Vio Scroll Dn Vio Scroll If Vio Scroll Rt Vio Scr Un Lock Vio Set Cur Pos Vio Set Cur Type Vio Set Mode Vio Get Mode Vio Show Buf Vio Wrt Cell Str Vio Wrt Char Str Vio Wrt Char Str Att Vio Wrt N Attr Vio Wrt N Cell Vio Wrt N Char Vio Wrt TTY Vio Scr Lock Vio Pop Up	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · 0 Comments

From:  
<https://ftp.osfree.org/doku/> - osFree wiki



Permanent link:  
<https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:viogetcurpos&rev=1535769112>

Last update: 2018/09/01 02:31