



# ANSICALL


This is forwarder DLL to DOSCALLS.DLL. No any real code here.

Ordinal	Type	Entry	Description	Status
1	16	AnsiInject	Inject ANSI Device Status Record output to KbdHandler buffer. Forwarder to DOSCALLS.848	Done
2	16	AnsiKeydef	ANSI keyboard key reassignment. Forwarder to DOSCALLS.849	Done
3	16	AnsiInterp	ANSI Control Code Sequence interpreter. Forwarder to DOSCALLS.850	Done
11	32	Ansi32Inject	Inject ANSI Device Status Record output to KbdHandler buffer. Forwarder to DOSCALLS.	
12	32	Ansi32Keydef	ANSI keyboard key reassignment. Forwarder to DOSCALLS.	
13	32	Ansi32Interp	ANSI Control Code Sequence interpreter. Forwarder to DOSCALLS.	

## OS/2 DLLs

Base API	DOSCALLS EMXWRAP SUB32 ANSICALL NLS MSG MONCALLS KBDCALLS MOUCALLS VIOCALLS SESMGR BKSCALLS BMSCALLS BVSCALLS NAMPIPES QUECALLS OS2CHAR
Bidirectional NLS	BDCALLS BDCALLS32 BDIME BDBVH BDVIEW BDWPCLS BIDIPM PMBIDI
Unicode API	UCONV UNIKBD LIBUNI
BVH (Base Video Handlers)	BVHINIT BVHMRA BVHVGA BVHSVGA BVHWNDW
GRADD subsystem	VMAN SOFTDRAW GRE2VMAN GENGRADD
IPF (Information Presentation facility)	HELPMGR HPMGRMRI MINXOBJ IBMHMGR NEWVIEW MINXMRI ERRTXT
REXX	REXX REXXAPI REXXUTIL REGINA
The core PM DLL's	PMMERGE PMMRGRES PMSHAPI PMSHLTKT PMGRE PMGPI PMDRAG PMCTLs PMMLE PMSPL PMVIOP PMWIN
Open32	PMWINX MIRRORS REGISTRY
Intelligent Font Interface drivers	PMATM TRUETYPE PMUNIF FREETYPE PMPRE
Data Exchange	PMCLIP PMDDE PMDDEML
VDM PM interface	PMVDMH PMVDMP SEAMLESS SHIELD
WPS	PMWP PMWPMRU PMVDDROP
Miscellaneous	PPMIC PMTKT MVDM
SOM API	SOM SOMC





2016/07/25 02:16 · prokushev · 0 Comments

From:  
<https://ftp.osfree.org/doku/> - **osFree wiki**



Permanent link:  
<https://ftp.osfree.org/doku/doku.php?id=en:docs:os2:modules:ansicall&rev=1533962897>

Last update: **2018/08/11 04:48**