



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

MouGetPtrPos

This call queries the mouse driver to determine the current row and column coordinate position of the mouse pointer.

Syntax

```
MouGetPtrPos (PtrPos, DeviceHandle);
```

Parameters

- PtrPos ([PPTRLOC](#)) - output: Address of the mouse pointer position structure.
- DeviceHandle ([HMOU](#)) - input: Contains the handle of the mouse device obtained from a previous MouOpen.

Return Code

rc (USHORT) - return:Return code descriptions are:

- 0 NO_ERROR
- 385 ERROR_MOUSE_NO_DEVICE
- 466 ERROR_MOU_DETACHED
- 501 ERROR_MOUSE_NO_CONSOLE
- 505 ERROR_MOU_EXTENDED_SG

Remarks

For a text window (VIO) application, the text window is a view on the larger logical video buffer (LVB). The mouse pointer can be outside that view and still be within the extent of the LVB. MouGetPtrPos then returns the coordinates of the cell under the mouse pointer. If the pointer is outside the LVB image extent, the coordinates of the nearest LVB cell are returned. In either case, the LVB is scrolled until the reported LVB cell appears within the view window.

Bindings

C

```
typedef struct _PTRLOC { /* moupl */
    USHORT row;          /* pointer row coordinate screen position */
    USHORT col;          /* pointer column coordinate screen position */
} PTRLOC;

#define INCL_MOU

USHORT rc = MouGetPtrPos(PtrPos, DeviceHandle);

PPTRLOC      PtrPos;      /* Double word structure */
HMOU         DeviceHandle; /* Mouse device handle */

USHORT       rc;          /* return code */
```

MASM

```
PTRLOC struc
    moupl_row dw ? ;pointer row coordinate screen position
    moupl_col dw ? ;pointer column coordinate screen position
PTRLOC ends

EXTRN MouGetPtrPos:FAR
INCL_MOU EQU 1

PUSH@ OTHER PtrPos ;Double word structure
PUSH WORD DeviceHandle ;Mouse device handle
CALL MouGetPtrPos

Returns WORD
```

Example

```
#define INCL_MOU
#include <os2.h>

PPTRLOC PtrPos; /* Pointer to the mouse pointer data structure. */
HMOU DeviceHandle; /* Reserved. Must be 0. */
APIRET rc; /* Return code. */

rc = MouGetPtrPos(PtrPos, DeviceHandle);
```

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From: <https://osfree.org/doku/> - **osFree wiki**

Permanent link: <https://osfree.org/doku/doku.php?id=en:docs:fapi:mougetptrpos>

Last update: **2021/11/04 13:10**

