



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

## VioSavRedrawUndo

This call allows one thread within a process to cancel a [VioSavRedrawWait](#) issued by another thread within the same process.

### Syntax

```
VioSavRedrawUndo (OwnerIndic, KillIndic, VioHandle)
```

### Parameters

- OwnerIndic ([USHORT](#)) - input: Indicates whether the thread issuing VioSavRedrawUndo wants ownership of VioSavRedrawWait to be reserved for its process.
  - 0 Reserve ownership
  - 1 Give up ownership.
- KillIndic ([USHORT](#)) - input: Indicates whether the thread with the outstanding VioSavRedrawWait should be returned an error code or be terminated.
  - 0 Return error code
  - 1 Terminate thread.
- VioHandle ([HVIO](#)) - input : Reserved word of 0s.

### Return Code

rc ([USHORT](#)) - return

Return code descriptions are:

- 0 NO\_ERROR
- 421 ERROR\_VIO\_INVALID\_PARMS
- 422 ERROR\_VIO\_FUNCTION\_OWNED
- 428 ERROR\_VIO\_NO\_SAVE\_RESTORE\_THD
- 430 ERROR\_VIO\_ILLEGAL\_DURING\_POPUP
- 465 ERROR\_VIO\_DETACHED
- 494 ERROR\_VIO\_EXTENDED\_SG

## Remarks

The issuing thread can reserve ownership of VioSavRedrawWait for its process or give it up. The thread whose VioSavRedrawWait was cancelled is optionally terminated. VioSavRedrawUndo may be issued only by a thread within the same process that owns VioSavRedrawWait.

## Bindings

### C

```
#define INCL_VIO

USHORT rc = VioSavRedrawUndo(OwnerIndic, KillIndic, VioHandle);

USHORT OwnerIndic;    /* Ownership indicator */
USHORT KillIndic;     /* Terminate indicator */
HVIO   VioHandle;     /* Video handle */

USHORT rc;            /* return code */
```

### MASM

```
EXTRN VioSavRedrawUndo:FAR
INCL_VIO EQU 1

PUSH WORD OwnerIndic ;Ownership indicator
PUSH WORD KillIndic ;Terminate indicator
PUSH WORD VioHandle ;Video handle
CALL VioSavRedrawUndo

Returns WORD
```

Text based on [http://www.edm2.com/index.php/VioSavRedrawUndo\\_\(OS/2\\_1.x\)](http://www.edm2.com/index.php/VioSavRedrawUndo_(OS/2_1.x))

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From: <https://www.osfree.org/doku/> - **osFree wiki**

Permanent link: <https://www.osfree.org/doku/doku.php?id=en:docs:fapi:viosavredrawundo>

Last update: **2021/09/28 01:59**

