



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushhev · [0 Comments](#)

2021/08/20 03:18 · prokushhev · [0 Comments](#)

DosGetVersion

This call returns the OS version number.

Syntax

```
DosGetVersion (VersionWord)
```

Parameters

- VersionWord ([USHORT](#)) - output:Address of the OS version number. The version is stored as two bytes, with the minor version in the first byte and major version in the second byte.

Return Code

- rc ([USHORT](#)) - return

Return code description is:

- 0 NO_ERROR

Bindings

C

```
#define INCL_DOSMISC

USHORT rc = DosGetVersion(VersionWord);
USHORT VersionWord; /* Version number (returned) */
USHORT rc; /* return code */
```

MASM

```
EXTRN DosGetVersion:Far
INCL_DOSMISC EQU 1

PUSH@ WORD VersionWord ;Version number(returned)
CALL DosGetVersion
```

Returns WORD

Example

The following example shows how one may obtain information for program initialization. The program locates the environment segment and prints the name of the command from the command line. It then obtains the OS version number and prints it.

```
#define INCL_DOS
#include <os2.h>
#define ENVVARNOME "PATH"

main()
{
    SEL      EnvSel;          /* Environment segment selector (returned) */
    USHORT   CmdOffset;       /* Offset into env. seg. of command line
(returned) */
    PSZ FAR *Commandline;    /* Pointer made by EnvSel and CmdOffset */
    USHORT   Version;         /* Version numbers (returned) */
    BYTE    MajorVer;         /* Major version number */
    BYTE    MinorVer;         /* Minor version number */
    USHORT   rc;              /* return code */

    /* Locate environment segment and offset of command line. */

    if(! (rc=DosGetEnv(&EnvSel,           /* Env. seg. selector (returned) */
                      &CmdOffset))) /* Offset of command line
(returned) */
        printf("Environment located; selector is %x offset is %x\n", EnvSel,
               CmdOffset);

    /* Use a macro to make a far pointer out of selector:offset pair.*/
    /* Notice the far-string pointer specification (%Fs) used to print */

    Commandline = MAKEP(EnvSel, CmdOffset);
    printf("Command entered is %Fs.\n", Commandline);

    /* Obtain and print version info; use macros to extract info. */
    /* We need to divide by 10 to obtain true version numbers. */
```

```

if( !(rc=DosGetVersion(&Version)))
{
    MajorVer = HIBYTE(Version) / 10;
    MinorVer = LOBYTE(Version) / 10;
    printf("This is OS/2 version %d.%d\n", MajorVer, MinorVer);
}

```

Note

Example code doesn't support check is executed under DOS or not.

Note

Text based on <http://www.edm2.com/index.php/DosGetVersion>

| Family API | | |
|------------|-----------------|---|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSet FileMode DosOpen DosQFileInfo DosRead DosQ FileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSet FileInfo DosSet Verify DosWrite DosFileLocks DosSet FHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGet HugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOCtl DosDevIOCtl2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| KBD | | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |
| VIO | | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |
| Tools | | BIND |
| Modules | | DOSCALLS.DLL VIOCALS.DLL KBDCALLS.DLL MSG.DLL |
| Libraries | | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB |

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:
<https://ftp.osfree.org/doku/> - osFree wiki



Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:fapi:dosgetversion&rev=1631859400>

Last update: **2021/09/17 06:16**